



# Distributed Tuning Interface Guide

Zen v15

Activate Your Data™



**Copyright © 2023 Actian Corporation. All Rights Reserved.**

This Documentation is for the end user's informational purposes only and may be subject to change or withdrawal by Actian Corporation ("Actian") at any time. This Documentation is the proprietary information of Actian and is protected by the copyright laws of the United States and international treaties. The software is furnished under a license agreement and may be used or copied only in accordance with the terms of that agreement. No part of this Documentation may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording, or for any purpose without the express written permission of Actian. To the extent permitted by applicable law, ACTIAN PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, AND ACTIAN DISCLAIMS ALL WARRANTIES AND CONDITIONS, WHETHER EXPRESS OR IMPLIED OR STATUTORY, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTY OF MERCHANTABILITY, OF FITNESS FOR A PARTICULAR PURPOSE, OR OF NON-INFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT WILL ACTIAN BE LIABLE TO THE END USER OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF ACTIAN IS EXPRESSLY ADVISED OF SUCH LOSS OR DAMAGE.

The manufacturer of this Documentation is Actian Corporation.

For government users, the Documentation is delivered with "Restricted Rights" as set forth in 48 C.F.R. Section 12.212, 48 C.F.R. Sections 52.227-19(c)(1) and (2) or DFARS Section 252.227-7013 or applicable successor provisions.

Actian, Actian DataCloud, Actian DataConnect, Actian X, Avalanche, Versant, PSQL, Actian Zen, Actian Director, Actian Vector, DataFlow, Ingres, OpenROAD, and Vectorwise are trademarks or registered trademarks of Actian Corporation and its subsidiaries. All other trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

---

---

# Contents

---

<b>About This Document</b>	<b>xxiii</b>
Who Should Read This Manual . . . . .	xxiii
<b>Distributed Tuning Interface Guide</b>	<b>1</b>
Overview of Distributed Tuning Interface . . . . .	1
String Arguments Encoding . . . . .	1
API Categories . . . . .	1
Execution Privileges. . . . .	1
Basics Of Using DTI . . . . .	2
Header Files . . . . .	2
Link Libraries. . . . .	2
Before Calling Any Functions . . . . .	3
Sample Programs For DTI . . . . .	3
Common Tasks With DTI. . . . .	4
Making a Connection to a Server Using DTI. . . . .	4
Obtaining a Setting ID Using DTI . . . . .	5
Passing a DTI Structure as a Parameter . . . . .	5
<b>Distributed Tuning Interface Reference</b>	<b>7</b>
Using the DTI Function Reference. . . . .	8
DTI Function Groups . . . . .	9
DTI Error Messages . . . . .	13
DTI Structures . . . . .	14
CONFIG.H Structures . . . . .	14
DDFSTRCT.H Structures. . . . .	14
MONITOR.H Structures . . . . .	17
DTI Calling Sequence . . . . .	18
DTI Function Definitions . . . . .	19
PvAddIndex() . . . . .	20
Syntax. . . . .	20
Arguments . . . . .	20
Return Values . . . . .	20
Remarks . . . . .	20
See Also . . . . .	21
PvAddLicense() . . . . .	22
Syntax. . . . .	22

---

Arguments .....	22
Return Values .....	22
Remarks.....	22
Example.....	23
See Also.....	23
PvAddTable() .....	24
Syntax .....	24
Arguments .....	24
Return Values .....	24
Remarks.....	25
See Also.....	25
PvAddUserToGroup() .....	26
Syntax .....	26
Arguments .....	26
Return Values .....	26
Remarks.....	26
See Also.....	27
PvAlterUserName() .....	28
Syntax .....	28
Arguments .....	28
Return Values .....	28
Remarks.....	28
See Also.....	29
PvAlterUserPassword() .....	30
Syntax .....	30
Arguments .....	30
Return Values .....	30
Remarks.....	30
See Also.....	31
PvCheckDbInfo() .....	32
Syntax .....	32
Arguments .....	32
Return Values .....	32
Remarks.....	33
Example.....	33
See Also.....	33
PvCloseDatabase() .....	35
Syntax .....	35
Arguments .....	35
Return Values .....	35

---

Remarks .....	35
See Also .....	35
PvCloseDictionary() .....	37
Syntax .....	37
Arguments .....	37
Return Values .....	37
Remarks .....	37
Example .....	37
See Also .....	38
PvConnectServer() .....	39
Syntax .....	39
Arguments .....	39
Return Values .....	39
Remarks .....	40
Example .....	40
See Also .....	41
PvCopyDatabase() .....	42
Syntax .....	42
Arguments .....	42
Return Values .....	42
Remarks .....	43
Example .....	43
See Also .....	43
PvCountDSNs() .....	44
Syntax .....	44
Arguments .....	44
Return Values .....	44
Remarks .....	44
See Also .....	45
PvCountSelectionItems() .....	46
Syntax .....	46
Arguments .....	46
Return Values .....	46
Remarks .....	46
See Also .....	47
PvCreateDatabase() .....	48
Syntax .....	48
Arguments .....	48
Return Values .....	49
Remarks .....	49

---

---

Example. ....	50
See Also. ....	51
PvCreateDatabase2() .....	52
Syntax .....	52
Arguments .....	52
Return Values .....	53
Remarks. ....	54
See Also. ....	54
PvCreateDictionary() .....	55
Syntax .....	55
Arguments .....	55
Return Values .....	55
Remarks. ....	56
See Also. ....	56
PvCreateDSN() .....	57
Syntax .....	57
Arguments .....	57
Return Values .....	58
Remarks. ....	58
See Also. ....	58
PvCreateDSN2() .....	59
Syntax .....	59
Arguments .....	59
Return Values .....	60
Remarks. ....	60
See Also. ....	61
PvCreateGroup() .....	62
Syntax .....	62
Arguments .....	62
Return Values .....	62
Remarks. ....	62
See Also. ....	63
PvCreateUser() .....	64
Syntax .....	64
Arguments .....	64
Return Values .....	64
Remarks. ....	65
See Also. ....	65
PvDeleteDSN() .....	66
Syntax .....	66

---

Arguments .....	66
Return Values .....	66
Remarks .....	66
See Also .....	67
PvDeleteLicense() .....	68
Syntax .....	68
Arguments .....	68
Return Values .....	68
Remarks .....	68
Example .....	69
See Also .....	69
PvDisconnect() .....	70
Syntax .....	70
Arguments .....	70
Return Values .....	70
Example .....	70
See Also .....	70
PvDisconnectMkdeClient() .....	72
Syntax .....	72
Arguments .....	72
Return Values .....	72
Example .....	72
Remarks .....	73
See Also .....	73
PvDisconnectSQLConnection() .....	74
Syntax .....	74
Arguments .....	74
Return Values .....	74
Example .....	74
Remarks .....	75
See Also .....	75
PvDropDatabase() .....	76
Syntax .....	76
Arguments .....	76
Return Values .....	76
Remarks .....	77
See Also .....	77
PvDropGroup() .....	78
Syntax .....	78
Arguments .....	78



---

Return Values .....	78
Remarks.....	78
See Also.....	79
PvDropIndex() .....	80
Syntax .....	80
Arguments .....	80
Return Values .....	80
Remarks.....	80
See Also.....	81
PvDropIndexByName() .....	82
Syntax .....	82
Arguments .....	82
Return Values .....	82
Remarks.....	82
See Also.....	83
PvDropTable() .....	84
Syntax .....	84
Arguments .....	84
Return Values .....	84
Remarks.....	84
See Also.....	85
PvDropUser() .....	86
Syntax .....	86
Arguments .....	86
Return Values .....	86
Remarks.....	86
See Also.....	87
PvFreeDbNamesData() .....	88
Syntax .....	88
Arguments .....	88
Return Values .....	88
Remarks.....	88
See Also.....	89
PvFreeMkdeClientsData() .....	90
Syntax .....	90
Arguments .....	90
Return Values .....	90
Remarks.....	90
See Also.....	91
PvFreeOpenFilesData() .....	92

---

Syntax . . . . .	92
Arguments . . . . .	92
Return Values . . . . .	92
Remarks . . . . .	92
See Also . . . . .	93
PvFreeSQLConnectionsData() . . . . .	94
Syntax . . . . .	94
Arguments . . . . .	94
Return Values . . . . .	94
Remarks . . . . .	94
See Also . . . . .	95
PvFreeTable() . . . . .	96
Syntax . . . . .	96
Arguments . . . . .	96
Return Values . . . . .	96
Remarks . . . . .	96
Example . . . . .	96
See Also . . . . .	97
PvFreeTableNames() . . . . .	98
Syntax . . . . .	98
Arguments . . . . .	98
Return Values . . . . .	98
Remarks . . . . .	98
Example . . . . .	98
See Also . . . . .	98
PvGetAllPossibleSelections() . . . . .	100
Syntax . . . . .	100
Arguments . . . . .	100
Return Values . . . . .	100
Remarks . . . . .	101
See Also . . . . .	101
PvGetBooleanStrings() . . . . .	102
Syntax . . . . .	102
Arguments . . . . .	102
Return Values . . . . .	102
Remarks . . . . .	103
See Also . . . . .	103
PvGetBooleanValue() . . . . .	104
Syntax . . . . .	104
Arguments . . . . .	104

---

Return Values .....	104
Remarks.....	105
See Also.....	105
PvGetCategoryInfo() .....	106
Syntax .....	106
Arguments .....	106
Return Values .....	106
Remarks.....	106
See Also.....	107
PvGetCategoryList() .....	108
Syntax .....	108
Arguments .....	108
Return Values .....	108
Remarks.....	108
See Also.....	109
PvGetCategoryListCount() .....	110
Syntax .....	110
Arguments .....	110
Return Values .....	110
Remarks.....	110
See Also.....	111
PvGetDbCodePage() .....	112
Syntax .....	112
Arguments .....	112
Return Values .....	112
Remarks.....	112
See Also.....	113
PvGetDbDataPath() .....	114
Syntax .....	114
Arguments .....	114
Return Values .....	114
See Also.....	115
PvGetDbDictionaryPath() .....	116
Syntax .....	116
Arguments .....	116
Return Values .....	116
Remarks.....	117
See Also.....	117
PvGetDbFlags() .....	118
Syntax .....	118

---

Arguments .....	118
Return Values .....	118
Remarks .....	119
See Also .....	119
PvGetDbName() .....	120
Syntax .....	120
Arguments .....	120
Return Values .....	120
Example .....	121
Remarks .....	121
See Also .....	121
PvGetDbNamesData() .....	122
Syntax .....	122
Arguments .....	122
Return Values .....	122
Remarks .....	122
See Also .....	123
PvGetDbServerName() .....	124
Syntax .....	124
Arguments .....	124
Return Values .....	124
Remarks .....	125
See Also .....	125
PvGetDSN() .....	126
Syntax .....	126
Arguments .....	126
Return Values .....	126
Remarks .....	127
See Also .....	127
PvGetDSNEx() .....	128
Syntax .....	128
Arguments .....	128
Return Values .....	129
Remarks .....	129
See Also .....	130
PvGetDSNEx2() .....	131
Syntax .....	131
Arguments .....	131
Return Values .....	132
Remarks .....	132

---

See Also.....	133
PvGetEngineInformation() .....	134
Syntax .....	134
Arguments .....	134
Return Values .....	135
Remarks.....	135
See Also.....	135
PvGetError() .....	136
Syntax .....	136
Arguments .....	136
Return Values .....	136
Remarks.....	136
See Also.....	137
PvGetFileHandlesData() .....	138
Syntax .....	138
Arguments .....	138
Return Values .....	138
Remarks.....	138
See Also.....	139
PvGetFileHandleInfo() .....	140
Syntax .....	140
Arguments .....	140
Return Values .....	140
Remarks.....	141
See Also.....	141
PvGetFileInfo() .....	142
Syntax .....	142
Arguments .....	142
Return Values .....	142
Remarks.....	142
See Also.....	143
PvGetLongValue() .....	144
Syntax .....	144
Arguments .....	144
Return Values .....	144
Remarks.....	145
See Also.....	145
PvGetMkdeClientId() .....	146
Syntax .....	146
Arguments .....	146

---

Return Values .....	146
Remarks .....	146
See Also .....	147
PvGetMkdeClientInfo() .....	148
Syntax .....	148
Arguments .....	148
Return Values .....	148
Remarks .....	148
See Also .....	149
PvGetMkdeClientHandlesData() .....	150
Syntax .....	150
Arguments .....	150
Return Values .....	150
Remarks .....	150
See Also .....	151
PvGetMkdeClientHandleInfo() .....	152
Syntax .....	152
Arguments .....	152
Return Values .....	152
Remarks .....	153
See Also .....	153
PvGetMkdeClientsData() .....	154
Syntax .....	154
Arguments .....	154
Return Values .....	154
Remarks .....	154
See Also .....	155
PvGetMkdeCommStat() .....	156
Syntax .....	156
Arguments .....	156
Return Values .....	156
Remarks .....	156
See Also .....	157
PvGetMkdeCommStatEx() .....	158
Syntax .....	158
Arguments .....	158
Return Values .....	158
Remarks .....	158
See Also .....	159
PvGetMkdeUsage() .....	160

---

Syntax .....	160
Arguments .....	160
Return Values .....	160
Remarks.....	160
See Also.....	161
PvGetMkdeUsageEx() .....	162
Syntax .....	162
Arguments .....	162
Return Values .....	162
Remarks.....	162
See Also.....	163
PvGetMkdeVersion() .....	164
Syntax .....	164
Arguments .....	164
Return Values .....	164
Remarks.....	164
See Also.....	165
PvGetOpenFilesData() .....	166
Syntax .....	166
Arguments .....	166
Return Values .....	166
Remarks.....	166
See Also.....	167
PvGetOpenFileName() .....	168
Syntax .....	168
Arguments .....	168
Return Values .....	168
Remarks.....	169
See Also.....	169
PvGetProductsInfo() .....	170
Syntax .....	170
Arguments .....	170
Return Values .....	170
Remarks.....	170
Example.....	174
See Also.....	176
PvGetSelectionString() .....	177
Syntax .....	177
Arguments .....	177
Return Values .....	177

---

Remarks .....	178
See Also .....	178
PvGetSelectionStringSize() .....	179
Syntax .....	179
Arguments .....	179
Return Values .....	179
Remarks .....	179
See Also .....	180
PvGetSelectionValue() .....	181
Syntax .....	181
Arguments .....	181
Return Values .....	181
Remarks .....	182
See Also .....	182
PvGetServerName() .....	183
Syntax .....	183
Arguments .....	183
Return Values .....	183
Remarks .....	183
See Also .....	184
PvGetSettingHelp() .....	185
Syntax .....	185
Arguments .....	185
Return Values .....	185
Remarks .....	185
See Also .....	186
PvGetSettingHelpSize() .....	187
Syntax .....	187
Arguments .....	187
Return Values .....	187
Remarks .....	187
See Also .....	188
PvGetSettingInfo() .....	189
Syntax .....	189
Arguments .....	189
Return Values .....	189
Remarks .....	189
See Also .....	190
PvGetSettingList() .....	191
Syntax .....	191

---



---

Arguments .....	191
Return Values .....	191
Remarks.....	192
See Also.....	192
PvGetSettingListCount() .....	193
Syntax .....	193
Arguments .....	193
Return Values .....	193
Remarks.....	193
See Also.....	194
PvGetSettingMap() .....	195
Syntax .....	195
Arguments .....	195
Return Values .....	195
Remarks.....	195
See Also.....	195
PvGetSettingUnits() .....	197
Syntax .....	197
Arguments .....	197
Return Values .....	198
Remarks.....	198
See Also.....	198
PvGetSettingUnitsSize() .....	199
Syntax .....	199
Arguments .....	199
Return Values .....	199
Remarks.....	200
See Also.....	200
PvGetSQLConnectionsData() .....	201
Syntax .....	201
Arguments .....	201
Return Values .....	201
Remarks.....	201
See Also.....	202
PvGetSQLConnectionInfo() .....	203
Syntax .....	203
Arguments .....	203
Return Values .....	203
Remarks.....	203
See Also.....	204

---

PvGetStringType()	205
Syntax	205
Arguments	205
Return Values	205
Remarks	205
See Also	206
PvGetStringValue()	207
Syntax	207
Arguments	207
Return Values	207
Remarks	208
See Also	208
PvGetStringValueSize()	209
Syntax	209
Arguments	209
Return Values	209
Remarks	210
See Also	210
PvGetTable()	211
Syntax	211
Arguments	212
Return Values	212
Remarks	212
See Also	212
PvGetTableNames()	213
Syntax	213
Arguments	213
Return Values	213
Remarks	213
See Also	214
PvGetTableStat()	215
Syntax	215
Arguments	215
Return Values	215
Remarks	215
See Also	216
PvGetTableStat2()	217
Syntax	217
Arguments	217
Return Values	217

---

Remarks. . . . .	217
See Also. . . . .	218
PvGetTableStat3() . . . . .	219
Syntax . . . . .	219
Arguments . . . . .	219
Return Values . . . . .	219
Remarks. . . . .	219
See Also. . . . .	220
PvGetValueLimit() . . . . .	221
Syntax . . . . .	221
Arguments . . . . .	221
Return Values . . . . .	221
Remarks. . . . .	222
See Also. . . . .	222
PvIsDatabaseSecured() . . . . .	223
Syntax . . . . .	223
Arguments . . . . .	223
Return Values . . . . .	223
Remarks. . . . .	223
See Also. . . . .	224
PvIsSettingAvailable() . . . . .	225
Syntax . . . . .	225
Arguments . . . . .	225
Return Values . . . . .	225
Remarks. . . . .	225
See Also. . . . .	225
PvListDSNs() . . . . .	227
Syntax . . . . .	227
Arguments . . . . .	227
Return Values . . . . .	227
Remarks. . . . .	228
Example. . . . .	228
See Also. . . . .	228
PvModifyDatabase() . . . . .	229
Syntax . . . . .	229
Arguments . . . . .	229
Return Values . . . . .	230
Remarks. . . . .	230
See Also. . . . .	231
PvModifyDatabase2() . . . . .	232

---

Syntax . . . . .	232
Arguments . . . . .	232
Return Values . . . . .	233
Remarks . . . . .	234
See Also . . . . .	234
PvModifyDSN() . . . . .	235
Syntax . . . . .	235
Arguments . . . . .	235
Return Values . . . . .	235
Remarks . . . . .	236
See Also . . . . .	236
PvModifyDSN2() . . . . .	237
Syntax . . . . .	237
Arguments . . . . .	238
Return Values . . . . .	238
Remarks . . . . .	239
See Also . . . . .	239
PvOpenDatabase() . . . . .	240
Syntax . . . . .	240
Arguments . . . . .	240
Return Values . . . . .	240
Remarks . . . . .	241
See Also . . . . .	241
PvOpenDictionary() . . . . .	242
Syntax . . . . .	242
Arguments . . . . .	242
Return Values . . . . .	242
Remarks . . . . .	243
See Also . . . . .	243
PvRemoveUserFromGroup() . . . . .	244
Syntax . . . . .	244
Arguments . . . . .	244
Return Values . . . . .	244
Remarks . . . . .	244
See Also . . . . .	245
PvSecureDatabase() . . . . .	246
Syntax . . . . .	246
Arguments . . . . .	246
Return Values . . . . .	246
Remarks . . . . .	246

---

See Also.....	247
PvSecureDatabase2() .....	248
Syntax .....	248
Arguments .....	248
Return Values .....	248
Remarks.....	249
See Also.....	249
PvSetBooleanValue() .....	250
Syntax .....	250
Arguments .....	250
Return Values .....	250
Remarks.....	251
See Also.....	251
PvSetLongValue() .....	252
Syntax .....	252
Arguments .....	252
Return Values .....	252
Remarks.....	253
See Also.....	253
PvSetSelectionValue() .....	254
Syntax .....	254
Arguments .....	254
Return Values .....	254
Remarks.....	255
See Also.....	255
PvSetStringValue() .....	256
Syntax .....	256
Arguments .....	256
Return Values .....	256
Remarks.....	257
See Also.....	257
PvStart() .....	258
Syntax .....	258
Arguments .....	258
Return Values .....	258
Remarks.....	258
Example.....	258
See Also.....	258
PvStop() .....	259
Syntax .....	259

---

Arguments .....	259
Return Values .....	259
Remarks .....	259
Example .....	259
See Also .....	259
PvUnSecureDatabase() .....	260
Syntax .....	260
Arguments .....	260
Return Values .....	260
Remarks .....	260
See Also .....	261
PvValidateLicenses() .....	262
Syntax .....	262
Arguments .....	262
Return Values .....	262
Remarks .....	262
Example .....	263
See Also .....	263

---

# About This Document

---

This documentation covers the Zen Distributed Tuning Interface components provided in its Software Development Kit (SDK).

## Who Should Read This Manual

This document is designed for any user who is familiar with Zen and wants to develop administrative applications using the Distributed Tuning Interface.

This manual does not provide comprehensive usage instructions for the software or instructions for using other database access methods. It does provide a reference for using the Distributed Tuning Interface.

We would appreciate your comments and suggestions about this document. Your feedback can determine what we write about the use of our products and how we deliver information to you. Please post your feedback in the community forum on the [Zen website](#).





# Distributed Tuning Interface Guide

---

The following topics introduce the Zen Distributed Tuning Interface:

- [Overview of Distributed Tuning Interface](#)
- [Basics Of Using DTI](#)
- [Sample Programs For DTI](#)
- [Common Tasks With DTI](#)

You can also go directly to [Distributed Tuning Interface Reference](#) for detailed information on the use of DTI in Zen.

## Overview of Distributed Tuning Interface

The purpose of Distributed Tuning Interface (DTI) is to provide an application programming interface for configuration, monitoring, and diagnostics of Zen components.

**Note:** For brevity, throughout the rest of this manual Distributed Tuning Interface is referred to by as DTI.

## String Arguments Encoding

A user application uses the client's OS encoding at the API level. DTI handles internally the differences between OS encodings on the server and client.

If an older client is communicating with the server, the database engine assumes that the client is using an encoding compatible with those available on the server.

## API Categories

The categories of available APIs are summarized in [DTI Function Groups](#).

## Execution Privileges

Generally, you want your DTI application to be able to call any of the DTI functions and view or modify all configuration settings. To ensure this full access, connect to the server by providing a name and password of a user with administrative level privileges on the server machine. This applies if the DTI application is running locally through a Terminal Services session or running

remotely. An application running locally can omit the user name and password and still be able call any of the DTI functions and view or modify all configuration settings. See [Making a Connection to a Server Using DTI](#).

Without administrator level privileges, an application running locally through a Terminal Services session or running remotely returns an access error for most of the DTI functions. Only a subset of the functions work. For example, many of the functions that can modify configuration settings when full access is permitted are restricted to read-only access.

## Basics Of Using DTI

### Header Files

The DTI functions are defined in the following header files:

- btitypes.h
- catalog.h
- config.h
- connect.h
- ddf.h
- dticonst.h
- dtilicense.h
- dtisecurity.h
- monitor.h

### Link Libraries

The following table lists the link libraries for DTI and the release version in which the library was first available on Windows, Linux, and macOS. Link your application to the appropriate library as defined in the table.

Library <sup>1</sup>	Windows	Linux	macOS	Version of Library First Available
w3dbav90.lib <sup>2</sup>	32-bit			PSQL v9.0
w64dba.lib	64-bit			PSQL v10.0

Library <sup>1</sup>	Windows	Linux	macOS	Version of Library First Available
w3dbav80.lib <sup>2</sup>	32-bit			Pervasive.SQL V8.0
w3dbav78.lib <sup>2</sup>	32-bit			Pervasive.SQL 2000i (SP3)
w3dbav75.lib <sup>2</sup>	32-bit			Pervasive.SQL 2000
libpsqltdi.so		32-bit		Pervasive.SQL V8.5
libpsqltdi.so		64-bit		PSQL 10.10
libpsqltdi.dylib			64-bit	PSQL v12.01

<sup>1</sup> All libraries have been compiled with Microsoft Visual Studio 2015.

<sup>2</sup> Each 32-bit library is a superset of the previous library. For example, w3dbav90.lib is a superset of w3dbav75.lib, w3dbav78.lib, and w3dbav80.lib.

The functions for the DTI are documented in [Distributed Tuning Interface Reference](#).

## Before Calling Any Functions

When you want to invoke DTI, you must first call the [PvStart\(\)](#) function. Then you can call multiple DTI functions before ending the session.

When ending a session, you must call [PvStop\(\)](#) to close the session.

## Sample Programs For DTI

By default, the runtime files for the DTI access method are installed with the Zen database engine and with Zen Client. At a minimum, you need Zen Client to create a DTI application.

The header files and sample files are available by online download. Sample files pertaining to a particular development environment are installed in separate directories, as shown in the following table.

Development Environment	Location
MS Visual C++ 8	<i>install_location</i> \SAMPLES\MSVC2005
MS Visual C++ 7	<i>install_location</i> \SAMPLES\MSVC2003
MS Visual C++ 6	<i>install_location</i> \SAMPLES\MSVC
Delphi 5	<i>install_location</i> \SAMPLES\DELPHI5

For additional information, see the DTI release notes (readme\_dti.htm) installed with the Zen database engine.

## Common Tasks With DTI

This topic outlines key tasks that are often used with DTI.

### Making a Connection to a Server Using DTI

This documents the procedure for obtaining a connection handle to a server, which is a first step for many DTI functions.

#### To obtain a Connection handle to a server

1. Start a DTI session

```
// initialize status code return
BTI_LONG status = 0;
// Call PvStart function with its reserved
// parameter
status = PvStart(0);
```

2. Connect to a server

```
// initialize variables
BTI_LONG status = 0;
BTI_CHAR_PTR uName = "jsmith";
BTI_CHAR_PTR pword = "123";
BTI_CHAR_PTR svrName = "myserver";
BTI_LONG hConn = 0xFFFFFFFF;
// after execution, hConn contains connection
// handle to pass to other functions
status = PvConnectServer(svrName, uName, pword, &hConn);
// if status != 0, handle errors now
```

Connection handles are required by many DTI functions. You can have multiple connections open at a time. For each connection or handle, however, you should call the PvDisconnect() function to release the handle.

```
status = PvDisconnect(phConn);
```

## Obtaining a Setting ID Using DTI

Many of the configuration functions take a setting ID as a parameter. This procedure describes the prerequisite functions for obtaining a setting ID.

### To obtain the ID for a Specific Setting

1. Perform the procedure [Making a Connection to a Server Using DTI](#) to obtain a connection handle.
2. Using the connection handle returned by `PvConnectServer()`, obtain a list of categories by calling `PvGetCategoryList()`.
3. For each category, get the list of settings using `PvGetSettingList()` and the settings count using `PvGetSettingListCount()`.
4. Scan for the setting that you want.
5. Retrieve information about the setting using `PvGetSettingInfo()`.
6. When done, disconnect from the server by calling `PvDisconnect()`.
7. End the DTI session by calling `PvStop()`.

## Passing a DTI Structure as a Parameter

Many functions require that you pass a DTI structure when making the functional call. The following code segment shows an example of a function call including a structure. See [DTI Structures](#) for more information about DTI structures.

```
WORD rValue = P_OK;
TABLEMAP* tableList;
WORD tableCount;
rValue = PvGetTableNames(m_DictHandle, &tableList, &tableCount);
```



# Distributed Tuning Interface Reference

---

The purpose of DTI is to provide an interface for configuring, monitoring, and diagnosing Zen components. DTI provides the functionality of Zen utilities from within your application.

The following topics cover the interface and its use:

- [Using the DTI Function Reference](#)
- [DTI Function Groups](#)
- [DTI Error Messages](#)
- [DTI Structures](#)
- [DTI Calling Sequence](#)
- [DTI Function Definitions](#)



---

## Using the DTI Function Reference

For each function, the following information is provided:

- Brief description – provides a short description of the function.
- Syntax – shows the C prototype syntax for the function.
- Arguments – provides detailed descriptions of the function arguments, and indicates which values are modified by the function. Parameters marked "in" are input-only, not modified by the function. Parameters marked "out" contain values modified by the function. Parameters marked "in/out" contain values that are both used by the function as input and modified by the function.
- Return Values – lists the possible return values and their meanings.
- Remarks – provides additional explanation about a function's parameters, effects, or usage.
- Example – provides a sample code segment showing the function's use.
- See Also – lists related functions and topics.

---

## DTI Function Groups

The Distributed Tuning Interface is divided into function groupings. For a summary of these groupings, please see the following table. The function descriptions begin in the following section in alphabetical order.

Function Group	Purpose	List of Functions
Catalog catalog.h	Managing the database catalog information, such as creating, opening, copying, or closing named databases, and creating, modifying or deleting data source names (DSNs),	<a href="#">PvCheckDbInfo()</a> <a href="#">PvCloseDatabase()</a> <a href="#">PvCopyDatabase()</a> <a href="#">PvCountDSNs()</a> <a href="#">PvCreateDatabase()</a> <a href="#">PvCreateDatabase2()</a> <a href="#">PvCreateDSN() (deprecated)</a> <a href="#">PvCreateDSN2() (deprecated)</a> <a href="#">PvDeleteDSN() (deprecated)</a> <a href="#">PvDropDatabase()</a> <a href="#">PvFreeDbNamesData()</a> <a href="#">PvGetDbCodePage()</a> <a href="#">PvGetDbDataPath()</a> <a href="#">PvGetDbDictionaryPath()</a> <a href="#">PvGetDbFlags()</a> <a href="#">PvGetDbName()</a> <a href="#">PvGetDbNamesData()</a> <a href="#">PvGetDbServerName()</a> <a href="#">PvGetDSN() (deprecated)</a> <a href="#">PvGetDSNEx() (deprecated)</a> <a href="#">PvGetDSNEx2() (deprecated)</a> <a href="#">PvGetEngineInformation()</a> <a href="#">PvListDSNs() (deprecated)</a> <a href="#">PvModifyDatabase()</a> <a href="#">PvModifyDatabase2()</a> <a href="#">PvModifyDSN() (deprecated)</a> <a href="#">PvModifyDSN2() (deprecated)</a> <a href="#">PvOpenDatabase()</a>

---

Function Group	Purpose	List of Functions
Configuration config.h	Controlling the configuration settings for the database engines, the communication managers, and the local requester components.	PvCountSelectionItems() PvGetAllPossibleSelections() PvGetBooleanStrings() PvGetBooleanValue() PvGetCategoryInfo() PvGetCategoryList() PvGetCategoryListCount() PvGetLongValue() PvGetSelectionString() PvGetSelectionStringSize() PvGetSelectionValue() PvGetSettingHelp() PvGetSettingHelpSize() PvGetSettingInfo() PvGetSettingList() PvGetSettingListCount() PvGetSettingMap() PvGetSettingUnits() PvGetSettingUnitsSize() PvGetStringType() PvGetStringValue() PvGetStringValueSize() PvGetValueLimit() PvIsSettingAvailable() PvSetBooleanValue() PvSetLongValue() PvSetSelectionValue() PvSetStringValue()
Connection connect.h	Starting and stopping a DTI session, connecting to a server, retrieving the name of the connected server, and disconnecting from a server.	PvConnectServer() PvDisconnect() PvGetServerName() PvStart() PvStop()

---

Function Group	Purpose	List of Functions
Dictionary ddf.h	Creating and closing dictionaries (DDFs), and creating or deleting tables, indexes, users and groups.	<a href="#">PvAddIndex()</a> <a href="#">PvAddTable()</a> <a href="#">PvAddUserToGroup()</a> <a href="#">PvAlterUserName()</a> <a href="#">PvAlterUserPassword()</a> <a href="#">PvCloseDictionary()</a> <a href="#">PvCreateDictionary() (deprecated)</a> <a href="#">PvCreateGroup()</a> <a href="#">PvCreateUser()</a> <a href="#">PvDropGroup()</a> <a href="#">PvDropIndex()</a> <a href="#">PvDropIndexByName()</a> <a href="#">PvDropTable()</a> <a href="#">PvDropUser()</a> <a href="#">PvFreeTable()</a> <a href="#">PvFreeTableNames()</a> <a href="#">PvGetError()</a> <a href="#">PvGetTable()</a> <a href="#">PvGetTableNames()</a> <a href="#">PvGetTableStat()</a> <a href="#">PvGetTableStat2()</a> <a href="#">PvGetTableStat3()</a> <a href="#">PvOpenDictionary() (deprecated)</a> <a href="#">PvRemoveUserFromGroup()</a>
License Administration dtlicense.h	Administering licensing such as authorizing or deauthorizing a key or retrieving information about keys.	<a href="#">PvAddLicense()</a> <a href="#">PvValidateLicenses()</a> <a href="#">PvDeleteLicense()</a> <a href="#">PvGetProductsInfo()</a>

---

Function Group	Purpose	List of Functions
Monitoring and Diagnostic monitor.h	<p>Monitoring files, clients, and SQL connections, such as the following information for the MicroKernel Engine:</p> <p>Active Files – count and list open files, query if file is open, query user who opened/locked the file, obtain page size, read-only flag, record locks, transaction locks, number of handles, obtain handle information for each handle.</p> <p>Active Clients – count and list clients, query active handles, obtain client information, obtain handle information, disconnect a client and all client functionality.</p> <p>Resource Usage – retrieve current, peak, and maximum settings for data, including files, handles, clients, worker threads, licenses in use, transactions, locks.</p> <p>Communications Statistics – retrieve all communications statistics, total, delta, current, peak, maximum where appropriate, reset delta functionality.</p>	<p>PvDisconnectMkdeClient()  PvDisconnectSQLConnection()  PvFreeMkdeClientsData()  PvFreeOpenFilesData()  PvFreeSQLConnectionsData()  PvGetFileHandlesData()  PvGetFileHandleInfo()  PvGetFileInfo()  PvGetMkdeClientId()  PvGetMkdeClientInfo()  PvGetMkdeClientHandlesData()  PvGetMkdeClientHandleInfo()  PvGetMkdeClientsData()  PvGetMkdeCommStat()  PvGetMkdeCommStatEx()  PvGetMkdeUsage()  PvGetMkdeUsageEx()  PvGetMkdeVersion()  PvGetOpenFilesData()  PvGetOpenFileName()  PvGetSQLConnectionsData()  PvGetSQLConnectionInfo()</p>
Security dtisecurity.h	Enabling, disabling, or querying the status of security on databases.	<p>PvIsDatabaseSecured()  PvSecureDatabase()  PvUnSecureDatabase()</p>

---

## DTI Error Messages

Refer to `dticonst.h` and `ddfstrct.h` for the defined status codes.

---

## DTI Structures

The following describes the structures used in DTI. Each structure grouping details the type of structures included and any notable settings or arguments that may be required. Structures are stored in the following header files:

- CONFIG.H
- DDFSTRCT.H
- MONITOR.H

For detailed information specific to each structure, refer to the corresponding header file for that structure.

### CONFIG.H Structures

The following lists the structures included in CONFIG.H. For detailed information about any of these structures, refer to the config header file.

- PVCATEGORYINFO
- PVSETTINGINFO

### DDFSTRCT.H Structures

The following lists the structures included in DDFSTRCT.H. For detailed information about any of these structures, refer to the ddf header file.

- TABLEMAP
- TABLEINFO
- TABLEINFO Flags

`B_FLAG_TRUE_NULLABLE = 64`

Table is true nullable. When the table is created, a one byte null indicator is added before each column that is nullable.

- TABLESTAT

The `systemDataKey` (later `systemData`) field has a value of 0 if no system data is present and a value of 1 if system data or system data v2 is present.

- TABLESTAT2

See [Differences Between TABLESTAT2 and TABLESTAT](#).

- 
- TABLESTAT3

See [Differences Between TABLESTAT3 and TABLESTAT2](#).

- COLUMNMAP
- COLUMNMAP Flags

```
B_FLAG_CASE_SENSITIVE = 1
```

Column values are case sensitive on comparisons and as part of index segments.

```
B_FLAG_NULLABLE = 4
```

If the table is created as true nullable, then a one byte null indicator column is added before the column value to indicate whether the column value is null.

```
B_FLAG_NTEXT = 2048
```

If a column is created as B\_TYPE\_BLOB, the data is treated as wide-character rather than character data.

```
B_FLAG_BINARY = 4096
```

If a column is created as B\_TYPE\_STRING or B\_TYPE\_BLOB, the data is treated as binary rather than character data.

- COLUMNMAP Data Types

COLUMNMAP DataType can take the following values:

```
B_TYPE_STRING = 0,  
B_TYPE_INTEGER = 1,  
B_TYPE_FLOAT = 2,  
B_TYPE_DATE = 3,  
B_TYPE_TIME = 4,  
B_TYPE_DECIMAL = 5,  
B_TYPE_MONEY = 6,  
B_TYPE_LOGICAL = 7,  
B_TYPE_NUMERIC = 8,  
B_TYPE_BFLOAT = 9,  
B_TYPE_LSTRING = 10,  
B_TYPE_ZSTRING = 11,  
B_TYPE_NOTE = 12,  
B_TYPE_LVAR = 13,  
B_TYPE_BINARY = 14,  
B_TYPE_AUTOINC = 15,  
B_TYPE_BIT = 16,  
B_TYPE_NUMERSTS = 17,  
B_TYPE_NUMERSA = 18,  
B_TYPE_CURRENCY = 19,  
B_TYPE_TIMESTAMP = 20,  
B_TYPE_BLOB = 21,  
B_TYPE_GDECIMAL = 22,  
B_TYPE_WSTRING = 25,  
B_TYPE_WZSTRING = 26,  
B_TYPE_GUID = 27,  
B_TYPE_DATETIME = 30
```



- 
- INDEXMAP
  - INDEXMAP Flags

`B_FLAG_DUPLICATES = 1`

Duplicates allowed in index.

`B_FLAG_MODIFIABLE = 2`

Index is modifiable.

`B_FLAG_SORT_DESCENDING = 64`

Sort index descending.

`B_FLAG_PARTIAL = 512`

Index is partial. Partial Index flags on segments that are not the last segment in the index, are ignored. Partial Indexes only apply to the last segment in an index.

## Differences Between TABLESTAT2 and TABLESTAT

Note the following differences between the TABLESTAT2 structure and the TABLESTAT structure:

- The fields for **tableName** and **tableLocation** allow more characters.
- The **numberOfRecords** field increases from 16 bits to 32 bits.
- File attribute fields were previously characters with values of "Y" or "N" to indicate whether the attribute is present or not. Attribute fields are now single byte integers with values of 1 or 0. A value of 1 means the attribute is present.
- The **freespaceThreshold** field is now an integer data type.
- The field **fileVersion** is no longer a float data type. It is now a single-byte integer that contains the same value that the Btrieve Stat (15) operation would return. For the 9.5 file format, the value returned is 0x95.
- A new field, **pageCompression**, indicates whether the physical file associated with the table has compressed pages or not.
- Previous fields **dataCompression** and **systemDataKey** have been renamed to **recordCompression** and **systemData**, respectively.

---

## Differences Between TABLESTAT3 and TABLESTAT2

Note the following differences between the TABLESTAT3 structure and the TABLESTAT2 structure:

- The **numberOfRecords** field increases from 32 bits to 64 bits.

### Backwards Compatibility

Zen clients can still make PvGetTableStat calls to the database engine. The database engine converts the reply message to a TABLESTAT2 structure or to a TABLESTAT structure as required based on the version of the client.

A Zen client determines the version of the database engine to which the client is connected. If the database engine version is prior to the current release, then PvGetTableStat2 returns a TABLESTAT structure and sets the value returned for pageCompression to 0.

## MONITOR.H Structures

The following lists the structures included in MONITOR.H. For detailed information about any of these structures, refer to the monitor header file.

- PVDATETIME
- PVFILEINFO
- PVFILEHDLINFO
- PVCLIENTID
- PVMKDECLIENTINFO
- PVMKDECLIENTHDLINFO
- PVMKDEUSAGE
- PVMKDEUSAGEEX
- PVVERSION
- PVCOMMSTAT
- PVCOMMSTATEX
- PVCOMMPROTOCOLSTAT
- PVSQLECONNINFO
- PVSQLECONNID

---

## DTI Calling Sequence

All Distributed Tuning Interface calls must initialize a DTI session by first calling `PvStart()`.

```
status = PvStart(0);  
// insert multiple DTI function calls here  
status = PvStop(0);
```

The Remarks section of every function lists additional prerequisites and post requisites for that particular function.

---

## **DTI Function Definitions**

This topic provides an alphabetical reference to the DTI functions.

---

## PvAddIndex()

Adds indexes specified in *indexList* to the existing table and to the underlying data file.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT PvAddIndex(  
    WORD          dictHandle,  
    LPCSTR        tableName,  
    INDEXMAP*     indexList,  
    WORD          indexCount);
```

### Arguments

---

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Name of the table where the indexes will be added.
In	<i>indexList</i>	Array of index definitions.
In	<i>indexCount</i>	Number of indexes in the <i>indexList</i> array.

---

### Return Values

---

PCM_Success	The operation completed successfully.
PCM_errFailed	The operation did not complete successfully.
PCM_errInvalidDictionaryHandle	The specified dictionary handle does not exist.
PCM_errTableNotFound	The specified table was not found.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errInvalidIndexName	The specified index name is invalid.
PCM_errColumnNotFound	The specified column was not found in the table.

---

### Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

---

The table specified by *tableName* must exist in the dictionary specified by *dictHandle*.

You will need to allocate and release `INDEXMAP` array used to describe the indexes.

## See Also

`PvStart()`

`PvOpenDatabase()`

`PvDropIndex()`

`PvDropIndexByName()`

`PvCloseDictionary()`

`PvStop()`

---

## PvAddLicense()

Applies (authorizes) the specified license from the computer indicated by the connection.

Header File: dtlicense.h (See also [Header Files](#))

Function First Available In Library: w3dbav80.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvAddLicense(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  license);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>license</i>	License to be applied (authorized).

---

### Return Values

---

P_OK	The operation completed successfully.
P_E_FAIL	The operation did not complete successfully.
P_E_LIC_ALREADY_INSTALLED	The license is already applied.
P_E_LIC_INVALID	The license specified is invalid.
Status code pertaining to license administration or to authorization	See <i>Status Codes and Messages</i> for <a href="#">License Administrator Status Codes</a> and <a href="#">Authorization Status Codes</a> .

---

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

## Example

```
BTI_CHAR_PTR add_lic = "ERXVD3U4ZS9KR94QPDHV5BN2";  
status = PvAddLicense(P_LOCAL_DB_CONNECTION, add_lic);
```

## See Also

[PvValidateLicenses\(\)](#)

[PvDeleteLicense\(\)](#)

[PvGetProductsInfo\(\)](#)

[PvStop\(\)](#)

[PvStart\(\)](#)



---

## PvAddTable()

Creates a new table in the existing dictionary and a data file at the location specified in the table properties.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
RESULT PvAddTable(  
    WORD          dictHandle,  
    TABLEINFO*  tableProps,  
    COLUMNMAP*   columnList,  
    WORD          columnCount,  
    INDEXMAP*    indexList,  
    WORD          indexCount);
```

### Arguments

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableProps</i>	Structure containing table information.
In	<i>columnList</i>	Array of columns defined in the table.
In	<i>columnCount</i>	Number of columns in <i>columnList</i> .
In	<i>indexList</i>	Array of index definitions.
In	<i>indexCount</i>	Number of indexes in the following <i>indexList</i> array.

### Return Values

<code>PCM_Success</code>	The operation was successful.
<code>PCM_errFailed</code>	The operation was not successful.
<code>PCM_errInvalidDictionaryHandle</code>	The specified dictionary handle does not exist.
<code>PCM_errTableNotFound</code>	The specified table was not found.
<code>PCM_errMemoryAllocation</code>	An error occurred during memory allocation.
<code>PCM_errInvalidColumnName</code>	The specified column name is invalid.

---

PCM_errInvalidDataType	The specified data type is invalid.
PCM_errDuplicateColumnName	The column name already exists in the table.
PCM_errInvalidDataSize	The data size is invalid.
PCM_errInvalidIndexName	Index name is invalid.
PCM_errColumnNotFound	Column specified for a segment cannot be found.

## Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

This function has to be provided with table information, columns, and indexes. The *indexCount* and *indexList* parameters are optional because indexes are not required to create a table.

This function will fail if a table with the same name is already present in the specified dictionary.

Table properties must be set up correctly and an array of at least one column must be passed.

You will need to allocate and release [COLUMNMAP](#) and [INDEXMAP](#) arrays and [TABLEINFO](#) structure used to describe table. See also [COLUMNMAP Flags](#).

The offset of a field within its row can be accessed through the [PvGetTable\(\)](#) function. The [COLUMNMAP](#) structure has been modified in `ddfstrct.h` to contain this additional information. This new field is ignored when calling the [PvAddTable\(\)](#) and [PvFreeTable\(\)](#) functions. Refer to `ddfstrct.h` and `ddf.h`.

## See Also

[PvStart\(\)](#)

[PvOpenDatabase\(\)](#)

[PvGetTableNames\(\)](#)

[PvFreeTableNames\(\)](#)

[PvDropTable\(\)](#)

[PvCloseDictionary\(\)](#)

[PvStop\(\)](#)

---

# PvAddUserToGroup()

Adds an existing user to an existing group in the database.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
PRESULT DDFAPICALTYPE PvAddUserToGroup(  
    BTI_WORD            dbHandle,  
    const BTI_CHAR*    user,  
    const BTI_CHAR*    group);
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>user</i>	Database user name
In	<i>group</i>	Database group name

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified account or user name does not exist.
PCM_errUserAlreadyPartOfGroup	User already part of the group.
PCM_errDatabaseHasNoSecurity	Database has no security.
PCM_errSessionSecurityError	Database opened with insufficient privilege.

## Remarks

This function will fail if the specified group or user do not already exist in the database, or if the user is a member of another group.

The following preconditions must be met:

- 
- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
  - The associated database has database-level security enabled.
  - The user and group already exist in the specified database.
  - The user is not a member of another group.

The following post condition must be met:

- Use [PvCloseDatabase\(\)](#) to free the resources.

## See Also

[PvAlterUserName\(\)](#)

[PvCreateGroup\(\)](#)

[PvCreateUser\(\)](#)

[PvDropGroup\(\)](#)

[PvDropUser\(\)](#)

[PvRemoveUserFromGroup\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCloseDatabase\(\)](#)

---

# PvAlterUserName()

Alters an existing user name in the specified database.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
PRESULT DDFAPICALLTYPE PvAlterUserName(  
    BTI_WORD  
    const BTI_CHAR*      dbHandle,  
    const BTI_CHAR*      user,  
    const BTI_CHAR*      newName);
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>user</i>	Database user name.
In	<i>newName</i>	New name for the database user. If set to NULL, the function fails.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The account or user name does not exist, or the new name is invalid.
PCM_errUserAlreadyExists	New user name already exists.
PCM_errDatabaseHasNoSecurity	Database has no security.
PCM_errSessionSecurityError	Database opened with insufficient privilege.

## Remarks

This function will fail if *newName* is set to NULL, or if *newName* is already present in the database.

---

The following preconditions must be met:

- You must first open a dictionary successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.
- The user name must already exist in the specified database.
- The new user name cannot already exist in the specified database.

The following post condition must be met:

- Use [PvCloseDatabase\(\)](#) to free the resources.

## See Also

[PvAlterUserPassword\(\)](#)

[PvAddUserToGroup\(\)](#)

[PvRemoveUserFromGroup\(\)](#)

[PvCreateUser\(\)](#)

[PvDropUser\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCloseDatabase\(\)](#)

---

# PvAlterUserPassword()

Alters an existing user password.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
PRELINT DDFAPICALTYPE PvAlterUserPassword(  
BTI_WORD  
const BTI_CHAR*      dbHandle,  
const BTI_CHAR*      user,  
const BTI_CHAR*      newPassword);
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>user</i>	Database user name.
In	<i>newPassword</i>	New user password. If set to NULL, the password is cleared.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified account or user name does not exist.
PCM_errDatabaseHasNoSecurity	Database has no security.
PCM_errSessionSecurityError	Database opened with insufficient privilege.

## Remarks

The following preconditions must be met:

- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.
- The user name must already exist in the specified database.

---

The following post condition must be met:

- Use [PvCloseDatabase\(\)](#) to free the resources.

## See Also

[PvAlterUserName\(\)](#)

[PvAddUserToGroup\(\)](#)

[PvRemoveUserFromGroup\(\)](#)

[PvCreateUser\(\)](#)

[PvDropUser\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCloseDatabase\(\)](#)



---

## PvCheckDbInfo()

Checks the consistency of a database.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvCheckDbInfo(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  dbName,  
    BTI_ULONG     checkFlags);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of an existing named database. A list of all named databases for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single named database from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
In	<i>checkFlags</i>	Reserved. The function checks for all database flags.

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Connection handle that identifies the server is invalid.
P_E_NULL_PTR	The function was called with a null pointer.
P_E_ACCESS_RIGHT	Insufficient access rights to call the function.
P_E_NOT_EXIST	Named database specified in <i>dbName</i> does not exist.
P_E_FAIL	A general failure occurred.

---

---

## Remarks

If the database is consistent, then the return value for this function is `P_OK`. If the database is not consistent or if the function call fails, then the return value is one of the error codes listed above.

## Example

```
BTI_WORD res; // returned value from function call
BTI_CHAR_PTR dbName; // database name
BTI_ULONG checkFlags; // database flags
BTI_LONG hConnection; // connection handle
BTI_LONG reserved;
// reserved value for PvStart() and PvStop()

// Initialize variables.
dbName = "demodata";
// The name of the database is demodata
checkFlags = 0xFFFFFFFF; // Checks all flags
hConnection = P_LOCAL_DB_CONNECTION;
// Set the connection handle to local connection

// P_LOCAL_DB_CONNECTION is defined in config.h
reserved = 0;

// Start a DTI session before making any DTI calls.
res = PvStart (reserved);

if (res == P_OK)
{
    // DTI session started successfully.
    // You can now make multiple DTI calls here.

    res = PvCheckDbInfo (hConnection,
                        dbName,
                        checkFlags);

    if (res == P_OK)
    {
        // Database is consistent.
    }
    else
    {
        // Put your code here to handle the error code
        // returned from PvCheckDbInfo ().
    }
    // Close DTI session.
    Res = PvStop (&reserved);
}
```

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbNamesData\(\)](#)

[PvGetDbName\(\)](#)

---

PvFreeDbNamesData()  
PvDisconnect()  
PvStop()

---

## PvCloseDatabase()

Closes an open database handle.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT PvCloseDatabase(  
    BTI_WORD    dbHandle);
```

### Arguments

---

In	<i>dbHandle</i>	Handle to a database opened by <a href="#">PvOpenDatabase()</a> .
----	-----------------	---

---

### Return Values

---

PCM_Success	The operation was successful.
PCM_errFailed	Operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation
PCM_errDictionaryNotOpen	No database open with specified handle.

---

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- Valid database handle returned by [PvOpenDatabase\(\)](#).

### See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

---

PvOpenDatabase()  
PvDisconnect()  
PvStop()

---

# PvCloseDictionary()

Closes an open dictionary.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
RESULT PvCloseDictionary(  
WORD dictHandle);
```

## Arguments

---

In	<i>dictHandle</i>	Handle of an open or newly-created dictionary.
----	-------------------	--

---

## Return Values

---

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errDictionaryNotOpen	The specified dictionary was not open.

---

## Remarks

This function requires a handle for an open dictionary file, which can be obtained with the [PvCreateDictionary\(\)](#) function.

Since multiple dictionaries can be open at one time, you need to call this function for every open or newly-created dictionary.

## Example

```
RESULT status = 0;  
status = PvCloseDictionary(myDictionaryHandle);
```

---

## See Also

[PvStart\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCreateDictionary\(\)](#)

[PvStop\(\)](#)

---

## PvConnectServer()

Attempts to connect to the target server that has the Zen database engine installed. If connection is established successfully, a connection handle is returned for subsequent references.

Header File: connect.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvConnectServer(  
    BTI_CHAR_PTR    serverName,  
    BTI_CHAR_PTR    userName,  
    BTI_CHAR_PTR    password,  
    BTI_LONG_PTR    phConnection);
```

### Arguments

In	<i>serverName</i>	Server name or IP address to which you want to connect. See also <a href="#">Drive-based Formats</a> in <i>Getting Started with Zen</i> .
In	<i>userName</i>	User name with which you will connect to <i>serverName</i> . See the Remarks section for information on omitting this parameter.
In	<i>password</i>	User password. See the Remarks section for information on omitting this parameter.
In/Out	<i>phConnectio n</i>	Address of a long integer that receives the connection handle if connection is successful.

### Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed to connect to the named server.
P_E_SERVER_NOT_FOUND	The specified server was not found
P_E_ENGINE_NOT_LOADED	The specified engine is not running.
P_E_REQUESTER_NOT_LOADED	The client requester is not loaded.



P_E_SERVER_TABLE_FULL	The internal server name table is full.
P_E_CLIENT_CONNECTIONS_LIMIT_REACHED	The operation could not connect because the limit on client connections has been reached. Check the configuration of the server.
P_E_PERMISSION_ERROR	The operation encountered a permissions error.
P_E_NO_MEMORY	The operation encountered a memory error.
P_E_NO_AVAILABLE_TRANSPORT	No remote connection could be established.
P_E_CONNECTION_LOST	The remote connection to the server was lost.

## Remarks

You must know the name of the server to which you want to connect. You can have open connections to multiple servers.

An application running locally where the database engine is running can omit the user name and password and still be able call any of the DTI functions and view or modify all configuration settings.

However, if the DTI application is running locally through a Terminal Services session or running remotely, provide the user name and password of a user with administrative level privileges on the server machine. This ensures that the application has full access for the DTI functions. Without administrator level privileges, an application returns an access error for most of the DTI functions. Only a subset of the functions work. For example, many of the functions that can modify configuration settings when full access is permitted are restricted to read-only access.

**Note:** You must call `PvStart()` to initialize DTI before attempting to connect to a server using this function.

## Example

```
BTI_CHAR_PTR uName = "jsmith";
BTI_CHAR_PTR pword = "123";
BTI_CHAR_PTR svrName = "myserver";
BTI_LONG_PTR phConn = 0xFFFFFFFF;
BTI_SINT status = 0;

status = PvConnectServer(svrName,
                        uName,
                        pword,
                        &phConn);
```

---

## See Also

PvStart()

PvGetServerName()

PvDisconnect()

PvStop()

---

# PvCopyDatabase()

Copies a database to a new database, adjusting the referential integrity if needed.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libsqldti.so (Linux), libsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvCopyDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbName,  
    BTI_CHAR_PTR     newdbName,  
    BTI_CHAR_PTR     newdictPath,  
    BTI_CHAR_PTR     newdataPath);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database to copy.
In	<i>newdbName</i>	Name of the new database.
In	<i>newdictPath</i>	Dictionary path of the new database.
In	<i>newdataPath</i>	Data path. Pass an empty string to use the default data path (that is, the same as the dictionary path)  If you want to create a new database that consists of MicroKernel Engine data files located in multiple paths, specify this parameter as a semicolon (;) delimited list. For example: C:\data\path1;C:\data\path2

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_ACCESS_RIGHT	Insufficient access right for the operation
P_E_DICTIONARY_ALREADY_EXISTS	Cannot create dictionary because it already exists.

P_E_SHARED_DDF_EXIST	The dictionary path is being used by another database.
P_E_DUPLICATE_NAME	Named database already exists on the server.
P_E_FAIL	Failed for other reasons.

## Remarks

The following preconditions must be met:

- The database and its files must be closed.
- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## Example

```
BTI_LONG connectionHandle = P_LOCAL_DB_CONNECTION;
BTI_CHAR_PTR newdataPath = "c:\\data\\gallery2";
BTI_CHAR_PTR newdictPath = "c:\\data\\gallery2";
BTI_CHAR_PTR databaseName = "Gallery";
BTI_CHAR_PTR newdatabaseName = "GalleryCopy";
BTI_SINT status = 0;
BTI_CHAR_PTR server = "MyServer";
BTI_CHAR_PTR user = "Administrator";
BTI_CHAR_PTR pwd = "Admin";
//only need to connect to server if it is remote
//otherwise can pass P_LOCAL_DB_CONNECTION for the handle

status = PvCopyDatabase(
connectionHandle,
databaseName,
newdatabaseName
dictPath,
dataPath);
```

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvCreateDatabase\(\)](#)  
[PvGetDbFlags\(\)](#)  
[PvModifyDatabase\(\)](#)  
[PvDropDatabase\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvCountDSNs()

Retrieves the number of datasource names (DSN).

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvCountDSNs(  
    BTI_LONG          hConnection,  
    BTI_ULONG_PTR    pdsnCount,  
    BTI_CHAR          filtering);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pdsnCount</i>	Address of an unsigned long to receive the number of DSNs.
In	<i>filtering</i>	Set to 1 if you want only Zen DSNs. Set to 0 if you want all DSNs.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_FAIL	Failed for other reasons.

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

To retrieve the number of DSNs without having to prompt the user to login, pass empty strings for username and password when establishing the server connection with [PvConnectServer\(\)](#).

**Note:** The connection established by passing empty strings for username and password is an insecure connection, and will not have sufficient rights to perform most of the other operations in DTI.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvListDSNs\(\)](#)

[PvGetDSN\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvCountSelectionItems()

Count the number of selection items for a setting of types (PVSETTING\_SINGLE\_SEL or PVSETTING\_MULTI\_SEL).

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvCountSelectionItems(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID,  
    BTI_ULONG_PTR pNumItems);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of categories can be obtained with the <a href="#">PvGetCategoryList()</a> function. A list of settings for a particular category can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pNumItems</i>	Address of an unsigned long that receives the number of selection items.

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_INVALID_DATA_TYPE	The requested setting is not of selection type.
P_E_FAIL	Failed for other reasons.

---

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

# PvCreateDatabase()

Creates a database by adding an entry to dbnames.cfg file. This entry is later used to create DSNs.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libsqldti.so (Linux), libsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvCreateDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_CHAR_PTR      dictPath,  
    BTI_CHAR_PTR      dataPath,  
    BTI_ULONG         dbFlags);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <b>PvConnectServer()</b> function.
In	<i>dbName</i>	Name of the database.
In	<i>dictPath</i>	Dictionary path.
In	<i>dataPath</i>	Data path. Pass an empty string to use the default data path (that is, the same as the dictionary path)  If you want to create a database that consists of MicroKernel Engine data files located in multiple paths, specify this parameter as a semicolon (;) delimited list. For example: C:\data\path1;C:\data\path2

---

---

In	<i>dbFlags</i>	Database flags, which can be a combination of the P_DBFLAG_ constants. <ul style="list-style-type: none"> <li>P_DBFLAG_RI (enforce integrity constraints, including referential integrity and triggers)</li> <li>P_DBFLAG_BOUND. Create DDF files and stamp the database name on the dictionary files so only that the database can use them. If the database is not bound, then more than one database can use the same dictionary file set. If you are creating a bound database and want to bind to DDF files that already exist, specify both P_DBFLAG_CREATE_DDF and P_DBFLAG_BOUND.</li> <li>P_DBFLAG_CREATE_DDF (create DDF files. The directory specified for <i>dictPath</i> has to exist.)</li> <li>P_DBFLAG_DBSEC_AUTHENTICATION (use database security authentication, Mixed security policy. See <a href="#">Btrieve Security Policy</a>.)</li> <li>P_DBFLAG_DBSEC_AUTHORIZATION (use database security authorization, Database security policy. See <a href="#">Btrieve Security Policy</a>.)</li> <li>P_DBFLAG_LONGMETADATA (use V2 metadata. See <a href="#">Metadata Version</a>.)</li> </ul>
----	----------------	--

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_ACCESS_RIGHT	Insufficient access right for the operation
P_E_DICTIONARY_ALREADY_EXISTS	Cannot create dictionary because it already exists.
P_E_SHARED_DDF_EXIST	The dictionary path is being used by another database.
P_E_DUPLICATE_NAME	Named database already exists on the server.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

## Retrieve Security Policy

The following table indicates how to specify a security model in a new database, or to interpret the security model of an existing database. Using any other combination of flags for security will result in status code 7024.

This Flag Combination	Represents This Security Model
No flags	Classic
P_DBFLAG_DBSEC_AUTHENTICATION	Mixed
P_DBFLAG_DBSEC_AUTHENTICATION P_DBFLAG_DBSEC_AUTHORIZATION	Database

## Metadata Version

If you specify P\_DBFLAG\_LONGMETADATA, then the database property in dbnames.cfg is set to V2 metadata. If you specify both P\_DBFLAG\_LONGMETADATA and P\_DBFLAG\_CREATE\_DDF, then the DDFs created are also V2 metadata.

The result of DDF creation varies depending on the DDF versions that already exist in the dictionary location.

Dictionary Location Contains	Result of DDF Creation
No DDFs	New DDFs added to dictionary location
DDFs of other metadata version	New DDFs added to group of existing DDFs
DDFs of same metadata version	New DDFs overwrite existing DDFs. Information in old DDFs is lost.

For example, suppose that your dictionary location contains V1 metadata DDFs and you create V2 metadata DDFs. The dictionary location will then contain a combination of V1 metadata DDFs and V2 metadata DDFs. A particular database can use one set of DDFs or the other, but not both concurrently.

## Example

The following example creates a database and DDFs that uses V2 metadata.

```
BTI_LONG connectionHandle = P_LOCAL_DB_CONNECTION;  
BTI_CHAR_PTR dataPath = "c:\\data\\gallery";  
BTI_CHAR_PTR dictPath = "c:\\data\\gallery";  
BTI_CHAR_PTR databaseName = "Gallery";
```

---

```
BTI_SINT status = 0;
BTI_CHAR_PTR server = "MyServer";
BTI_CHAR_PTR user = "Administrator";
BTI_CHAR_PTR pwd = "Admin";
//only need to connect to server if it is remote
//otherwise can pass P_LOCAL_DB_CONNECTION for the handle

status = PvCreateDatabase(
connectionHandle,
databaseName,
dictPath,
dataPath,
P_DBFLAG_CREATE_DDF,
P_DBFLAG_LONGMETADATA);
```

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetDbFlags\(\)](#)  
[PvModifyDatabase\(\)](#)  
[PvDropDatabase\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvCreateDatabase2()

Creates a database by adding an entry to dbnames.cfg file. This function is the same as [PvCreateDatabase\(\)](#) except that the database code page is also specified.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvCreateDatabase2(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbName,  
    BTI_CHAR_PTR     dictPath,  
    BTI_CHAR_PTR     dataPath,  
    BTI_ULONG        dbFlags,  
    BTI_LONG          dbCodePage);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <b>PvConnectServer()</b> function.
In	<i>dbName</i>	Name of the database.
In	<i>dictPath</i>	Dictionary path.
In	<i>dataPath</i>	Data path. Pass an empty string to use the default data path (that is, the same as the dictionary path)  If you want to create a database that consists of MicroKernel Engine data files located in multiple paths, specify this parameter as a semicolon (;) delimited list. For example: C:\data\path1;C:\data\path2

---

---

In	<i>dbFlags</i>	<p>Database flags, which can be a combination of the P_DBFLAG_ constants.</p> <ul style="list-style-type: none"> <li>• P_DBFLAG_RI (enforce integrity constraints, including referential integrity and triggers)</li> <li>• P_DBFLAG_BOUND (create DDF files and stamp the database name on the dictionary files so only that database can use them. If the database is not bound, then several databases can use the same dictionary file set.) If trying to create a bound database and you want to bind to DDF files that already exist, specify both P_DBFLAG_CREATE_DDF and P_DBFLAG_BOUND.</li> <li>• P_DBFLAG_CREATE_DDF (create DDF files. The directory specified for <i>dictPath</i> has to exist.)</li> <li>• P_DBFLAG_DBSEC_AUTHENTICATION (use database security authentication, Mixed security policy. See <a href="#">Btrieve Security Policy</a>.)</li> <li>• P_DBFLAG_DBSEC_AUTHORIZATION (use database security authorization, Database security policy. See <a href="#">Btrieve Security Policy</a>.)</li> <li>• P_DBFLAG_LONGMETADATA (use V2 metadata. See <a href="#">Metadata Version</a>.)</li> </ul>
----	----------------	---

---

In	<i>dbCodePage</i>	<p>For databases on Windows platforms, a number indicating the code page for database data and metadata strings.</p> <p>For databases on Linux and macOS distributions, one of the following to indicate the code page for database data and metadata strings:</p> <ul style="list-style-type: none"> <li>• P_DBCODEPAGE_UTF8</li> <li>• P_DBCODEPAGE_EUCJP</li> <li>• P_DBCODEPAGE_ISO8859_1</li> </ul> <p>For databases on Windows, Linux, and macOS, a value of zero can also be used.</p> <p>Zero indicates legacy behavior. That is, no code page is specified, defaulting to the operating system encoding on the server machine. See also the <a href="#">Code Page</a> database property in <i>Zen User's Guide</i>.</p> <p><b>Note:</b> The database engine does <b>not</b> validate the encoding of the data and metadata that an application inserts into a database. The engine assumes that all data was entered using the encoding of the server or the client as explained under <a href="#">Database Code Page and Client Encoding</a> in <i>Advanced Operations Guide</i>.</p>
----	-------------------	---

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.

---

---

P_E_NULL_PTR	Call with NULL pointer
P_E_ACCESS_RIGHT	Insufficient access right for the operation
P_E_DICTIONARY_ALREADY_EXISTS	Cannot create dictionary because it already exists.
P_E_SHARED_DDF_EXIST	The dictionary path is being used by another database.
P_E_DUPLICATE_NAME	Named database already exists on the server.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## Btrieve Security Policy and Metadata Version

See [Btrieve Security Policy](#) and [Metadata Version](#), respectively.

## See Also

[PvConnectServer\(\)](#)  
[PvCreateDSN2\(\)](#)  
[PvDisconnect\(\)](#)  
[PvDropDatabase\(\)](#)  
[PvGetDbCodePage\(\)](#)  
[PvGetDbFlags\(\)](#)  
[PvGetDSNEx2\(\)](#)  
[PvModifyDatabase2\(\)](#)  
[PvStart\(\)](#)  
[PvStop\(\)](#)

---

## PvCreateDictionary()

Creates a new set of dictionary files. Given a fully-qualified path for the dictionary, it returns a dictionary handle that will be used for any subsequent calls to catalog functions.

**Note:** This function is deprecated in Zen 9 and higher versions. See [PvCreateDatabase\(\)](#) and [PvOpenDatabase\(\)](#) to replace this function in your application.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT PvCreateDictionary(  
    LPCSTR      path,  
    WORD*       dictHandle,  
    LPCSTR      user,  
    LPCSTR      password);
```

### Arguments

In	<i>path</i>	Fully-qualified path to the dictionary files.
Out	<i>dictHandle</i>	Handle to be used in subsequent calls
In	<i>user</i>	User name used with the new dictionary. This argument can be set to NULL.
In	<i>password</i>	Used in conjunction with user name to create new dictionary files. Can also be NULL.

### Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errPathNotFound	The specified path is invalid.
PCM_errSessionSecurityError	Either the user name or password is invalid.
PCM_errDictionaryAlreadyExists	A set of ddf files already exists at the specified location.



---

## Remarks

Use `PvCloseDictionary()` to free the resources.

## See Also

`PvStart()`

`PvOpenDatabase()`

`PvGetDbDictionaryPath()`

`PvCloseDictionary()`

`PvStop()`

---

## PvCreateDSN()

Creates a new engine data source name (DSN).

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to create client DSNs (or dsnadd utility on Linux and macOS).

### Syntax

```
BTI_API PvCreateDSN(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  pdsnName,  
    BTI_CHAR_PTR  pdsnDesc,  
    BTI_CHAR_PTR  pdsnDBQ,  
    BTI_LONG      openMode);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pdsnName</i>	Name for the new DSN.
In	<i>pdsnDesc</i>	Description for the new DSN.
In	<i>pdsnDBQ</i>	Database name to which this DSN will connect. This name must already exist. To create a database name, see <a href="#">PvCreateDatabase()</a> .
In	<i>OpenMode</i>	Open mode for the DSN, which is one of the following: <ul style="list-style-type: none"><li>• NORMAL_MODE</li><li>• ACCELERATED_MODE</li><li>• READONLY_MODE</li><li>• EXCLUSIVE_MODE</li></ul>

---

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_INVALID_NAME	The specified DSN name is invalid.
P_E_DSN_ALREADY_EXIST	The specified DSN name already exists.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_INVALID_OPEN_MODE	The specified open mode is invalid.
P_E_FAIL	Failed to retrieve data path.

## Remarks

This function creates engine DSNs only. To create a client DSN, you must use the ODBC API.

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- The database name referenced in the *psnDBQ* parameter must already exist. To create a database name, see [PvCreateDatabase\(\)](#).

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvListDSNs\(\)](#)  
[PvModifyDSN\(\)](#)  
[PvGetDSN\(\)](#)  
[PvGetDSNEx\(\)](#)  
[PvDeleteDSN\(\)](#)  
[PvCountDSNs\(\)](#)  
[PvStop\(\)](#)

---

## PvCreateDSN2()

Creates a new engine data source name (DSN) and specifies the encoding option for data.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to create client DSNs (or **dsnadd** utility on Linux and macOS).

### Syntax

```
BTI_API PvCreateDSN2(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  pdsnName,  
    BTI_CHAR_PTR  pdsnDesc,  
    BTI_CHAR_PTR  pdsnDBQ,  
    BTI_LONG      openMode,  
    BTI_LONG      translate);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pdsnName</i>	Name for the new DSN.
In	<i>pdsnDesc</i>	Description for the new DSN.
In	<i>dsnDBQ</i>	Database name to which this DSN will connect. This name must already exist. To create a database name, see <a href="#">PvCreateDatabase()</a> .
In	<i>OpenMode</i>	Open mode for the DSN, which is one of the following: <ul style="list-style-type: none"><li>NORMAL_MODE</li><li>ACCELERATED_MODE</li><li>READONLY_MODE</li><li>EXCLUSIVE_MODE</li></ul> See also <a href="#">DSN Open Mode</a> in <i>ODBC Guide</i> .

---

---

In	<i>translate</i>	Encoding option for data, which can be one of the following: <ul style="list-style-type: none"> <li>• DSNFLAG_DEFAULT</li> <li>• DSNFLAG_OEMANSI</li> <li>• DSNFLAG_AUTO</li> </ul> See also <a href="#">Encoding Translation</a> in <i>ODBC Guide</i> . Note that DSNFLAG_DEFAULT corresponds to the "None" encoding option in ODBC Administrator.
----	------------------	---

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_INVALID_NAME	The specified DSN name is invalid.
P_E_DSN_ALREADY_EXIST	The specified DSN name already exists.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_INVALID_OPEN_MODE	The specified open mode is invalid.
P_E_INVALID_TRANSLATE_OPTION	The specified encoding translation option is invalid.
P_E_FAIL	Failed to retrieve data path.

---

## Remarks

This function creates engine DSNs only and requires a PSQL v10 client or later. To create a client DSN, you must use the ODBC API. (On Linux and macOS, you can also use the `dsnadd` utility to create a client DSN.)

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- The database name referenced in the `pdsnDBQ` parameter must already exist. To create a database name, see [PvCreateDatabase\(\)](#).

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvListDSNs\(\)](#)

[PvModifyDSN\(\)](#)

[PvGetDSN\(\)](#)

[PvGetDSNEx\(\)](#)

[PvDeleteDSN\(\)](#)

[PvCountDSNs\(\)](#)

[PvStop\(\)](#)

---

# PvCreateGroup()

Creates a new user group in the existing database.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
RESULT DDFAPICALTYPE PvCreateGroup(  
BTI_WORD dbHandle,  
const BTI_CHAR* group);
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>Group</i>	Database group name.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified group name is invalid.
PCM_errDatabaseHasNoSecurity	Database has no security
PCM_errSessionSecurityError	Database opened with insufficient privilege
PCM_errGroupAlreadyExists	Group already exists

## Remarks

The following preconditions must be met:

- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.
- A group with the same name cannot already exist in the specified database.

---

The following post condition must be met:

- Use `PvCloseDatabase()` to free the resources.

## See Also

[PvAddUserToGroup\(\)](#)

[PvRemoveUserFromGroup\(\)](#)

[PvCreateUser\(\)](#)

[PvAlterUserName\(\)](#)

[PvAlterUserPassword\(\)](#)

[PvDropGroup\(\)](#)

[PvDropUser\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCloseDatabase\(\)](#)



---

## PvCreateUser()

Creates a new user in the existing database. Optionally set a password and assign the new user to an existing group.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
RESULT DDFAPICALTYPE PvCreateUser(  
    BTI_WORD          dbHandle,  
    const BTI_CHAR*   user,  
    const BTI_CHAR*   password,  
    const BTI_CHAR*   group);
```

### Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>user</i>	Database user name.
In	<i>password</i>	User password. If set to NULL, no password is set.
In	<i>group</i>	Database group name for user. If set to NULL, user is not assigned to a group.

### Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified account or user name is invalid.
PCM_errUserAlreadyExists	User already exists.
PCM_errDatabaseHasNoSecurity	Database has no security.
PCM_errSessionSecurityError	Database opened with insufficient privilege.

---

## Remarks

The following preconditions must be met:

- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.
- A user with the same name cannot already exist in the specified database.

The following post condition must be met:

- Use [PvCloseDatabase\(\)](#) to free the resources.

## See Also

[PvAlterUserName\(\)](#)

[PvAlterUserPassword\(\)](#)

[PvAddUserToGroup\(\)](#)

[PvRemoveUserFromGroup\(\)](#)

[PvCreateGroup\(\)](#)

[PvDropUser\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCloseDatabase\(\)](#)

---

## PvDeleteDSN()

Deletes a data source name.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

### Syntax

```
BTI_API PvDeleteDSN(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  pdsnName);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pdsnName</i>	DSN to delete.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_DSN_DOES_NOT_EXIST	The specified DSN name does not exist.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_FAIL	Failed to retrieve data path.

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvListDSNs\(\)](#)  
[PvModifyDSN\(\)](#)  
[PvGetDSN\(\)](#)  
[PvGetDSNEx\(\)](#)  
[PvCreateDSN\(\)](#)  
[PvCountDSNs\(\)](#)  
[PvStop\(\)](#)

---

## PvDeleteLicense()

Deletes (deauthorizes) the specified license from the computer indicated by the connection.

Header File: dtlicense.h (See also [Header Files](#))

Function First Available In Library: w3dbav80.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvDeleteLicense(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  licenses);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>licenses</i>	License to be deleted.

---

### Return Values

---

P_OK	The operation completed successfully
P_E_FAIL	The operation did not complete successfully
P_E_LIC_NOT_FOUND	The license specified is not currently authorized.
P_E_LIC_INVALID	The license specified is invalid.
Status code pertaining to license administration or to authorization	See <i>Status Codes and Messages</i> for <a href="#">License Administrator Status Codes</a> and <a href="#">Authorization Status Codes</a> .

---

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## Example

```
BTI_CHAR_PTR delete_lic = "ERXVD3U4ZS9KR94QPDHV5BN2";  
status = PvDeleteLicense(P_LOCAL_DB_CONNECTION, delete_lic);
```

## See Also

[PvAddLicense\(\)](#)

[PvValidateLicenses\(\)](#)

[PvGetProductsInfo\(\)](#)

[PvStop\(\)](#)

[PvStart\(\)](#)

---

# PvDisconnect()

Attempts to disconnect the connection established earlier by PvConnectServer function.

Header File: connect.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvDisconnect(  
    BTI_LONG      hConnection);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle to be disconnected. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
----	--------------------	--

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_FAIL	Failed to disconnect to the named server.

---

## Example

```
BTI_SINT status = 0;  
status = PvDisconnect(m_hConn);
```

## See Also

- [PvStart\(\)](#)
- [PvConnectServer\(\)](#)
- [PvGetMkdeClientsData\(\)](#)
- [PvGetMkdeCommStat\(\)](#)
- [PvGetMkdeUsage\(\)](#)
- [PvGetOpenFilesData\(\)](#)
- [PvFreeOpenFilesData\(\)](#)

---

PvDisconnectMkdeClient()  
PvDisconnectSQLConnection()  
PvStop()



---

# PvDisconnectMkdeClient()

Attempts to disconnect an active MicroKernel Engine client by specifying a client ID. In order to obtain a valid client ID, use PvGetMkdeClientData and PvGetMkdeClientId functions.

Header File: monitor.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvDisconnectMkdeClient(  
    BTI_LONG          hConnection,  
    PVCLIENTID*     pClientId);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pClientId</i>	Address of the <a href="#">PVCLIENTID</a> structure to identify the MicroKernel Engine client.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_CLIENT	Invalid client ID.
P_E_FAIL	Failed to disconnect to the named server.

## Example

```
unsigned long count = 0;  
  
// This sample disconnects all active Mkde connections  
BTI_SINT status = 0  
PVCLIENTID clientId;  
status = PvGetMkdeClientsData(connection, &count);
```

---

```
while (count > 0)
{
status = PvGetMkdeClientId(connection, 0, &client Id);
status = PvDisconnectMkdeClient(connection, &clientId);
status = PvGetMkdeClientsData(connection, &count)
}
PvFreeMkdeClientsData(connection);
```

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetMkdeClientsData\(\)](#)  
[PvGetMkdeClientId\(\)](#)  
[PvGetMkdeClientInfo\(\)](#)  
[PvGetMkdeClientHandlesData\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvDisconnectSQLConnection()

Attempts to disconnect an active SQL connection by passing SQL connection Id. Use `PvGetSQLConnectionsData` and `PvSQLConnectionInfo` to obtain a valid connection Id.

**Note:** Each SQL connection also establishes a MicroKernel Engine connection. Use `PvDisconnectMKDEClient` to kill those connections.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvDisconnectSQLConnection(  
    BTI_LONG          hConnection,  
    PVSQLECONNID*    pSQLConnId);
```

### Arguments

In	<i>hConnection</i>	Server connection handle that contains the SQL connection to be disconnected. Server connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pSQLConnId</i>	Address of the <a href="#">PVSQLECONNID</a> structure to identify the SQL connection. SQL connections are obtained with the <a href="#">PvGetSQLConnectionsData()</a>

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_CLIENT	Invalid client ID.
P_E_FAIL	Failed to disconnect to the named server.

### Example

```
BTI_SINT status = 0;
```

---

```
PVSQLCONNINFO connectionInfo;
PVSQLCONNID  connId;
status = PvGetSQLConnectionsData (connection, &count);
while (count > 0)
{
    status = PvGetSQLConnectionInfo(connection, 0,
                                    &connectionInfo);
    connId.u132ProcessId =
        connectionInfo.u132ProcessId;
    connId.u132ThreadId =
        connectionInfo.u132ThreadId;
    status = PvDisconnectSQLConnection(connection,
                                       &connId);
    status = PvGetSQLConnectionsData (connection,
                                       &count);
}
PvFreeSQLConnectionsData(connection, &count);
```

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetSQLConnectionsData\(\)](#)

[PvGetSQLConnectionInfo\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvDropDatabase()

Deletes a specified entry from dnames.cfg.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvDropDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbName,  
    BTI_CHAR         option);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database. A list of all database names for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single database name from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
In	<i>option</i>	Bit mask that specifies options. Set the low-order bit to one (0001h) if you want DDF files to be deleted in addition to the database name. Otherwise, only the database name will be deleted but DDF files will remain.

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_ACCESS_RIGHT	Insufficient access right for the operation
P_E_NOT_EXIST	Named database does not exist.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvCreateDatabase\(\)](#)

[PvModifyDatabase\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvDropGroup()

Drop an existing group from the database.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
PRELINT DDFAPICALTYPE PvDropGroup(  
BTI_WORD dbHandle,  
const BTI_CHAR* group);
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>group</i>	Database group name.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified group name does not exist.
PCM_errDatabaseHasNoSecurity	Database has no security
PCM_errSessionSecurityError	Database opened with insufficient privilege
PCM_errGroupNotEmpty	An user is associated with this group

## Remarks

The following preconditions must be met:

- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.
- The group must already exist in the specified database.
- The group cannot contain any members.

---

The following post condition must be met:

- Use `PvCloseDatabase()` to free the resources.

## See Also

`PvCreateGroup()`

`PvAddUserToGroup()`

`PvRemoveUserFromGroup()`

`PvDropUser()`

`PvOpenDatabase()`

`PvCloseDatabase()`



---

# PvDropIndex()

Drops the index from dictionary and data files, given the index number.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
PRESULT PvDropIndex(  
    WORD          dictHandle,  
    LPCSTR        tableName,  
    WORD          indexNumber,  
    BOOL          renumber);
```

## Arguments

---

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Name of the table with the index to be dropped.
In	<i>indexNumber</i>	Number of the index to be dropped.
In	<i>renumber</i>	Indicates whether the remaining indexes should be renumbered.

---

## Return Values

---

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidDictionaryHandle	The specified dictionary handle does not exist.
PCM_errTableNotFound	The specified table was not found.
PCM_errInvalidIndex	The specified index was not found.

---

## Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

The table specified by *tableName* must exist in the dictionary specified by *dictHandle*.

---

## See Also

PvStart()

PvOpenDatabase()

PvDropIndexByName()

PvAddIndex()

PvCloseDictionary()

PvStop()

---

# PvDropIndexByName()

Drops the index from dictionary and data files, given a name.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
PRESULT PvDropIndexByName(  
    WORD          dictHandle,  
    LPCSTR        tableName,  
    LPCSTR        indexName);
```

## Arguments

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Name of the table with the index to be dropped.
In	<i>indexName</i>	Name of the index to be dropped.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidDictionaryHandle	The specified dictionary handle does not exist.
PCM_errTableNotFound	The table specified in <i>tableName</i> was not found in the dictionary.

## Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

The table specified by *tableName* must exist in the dictionary specified by *dictHandle*.

---

## See Also

`PvStart()`

`PvOpenDatabase()`

`PvAddIndex()`

`PvDropIndex()`

`PvCloseDictionary()`

`PvStop()`

---

## PvDropTable()

Drops the specified table from the open dictionary specified by the dictionary handle.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
PRELIM PvDropTable(  
    WORD          dictHandle,  
    LPCSTR        tableName,  
    WORD          keepFile);
```

### Arguments

---

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Name of the table to delete.
In	<i>keepFile</i>	Indicates whether or not the data file will be deleted. If set to 0, the data file associated with the table will be deleted. If non-zero, the data file will not be deleted.

---

### Return Values

---

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidDictionaryHandle	The specified dictionary handle does not exist.
PCM_errTableNotFound	The specified table name was not found.

---

### Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

The table specified by *tableName* must exist in the dictionary specified by *dictHandle*.

---

## See Also

PvStart()

PvOpenDatabase()

PvGetTableNames()

PvGetTable()

PvAddTable()

PvCloseDictionary()

PvStop()

---

# PvDropUser()

Drop an existing user from the database.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
RESULT DDFAPICALTYPE PvDropUser (  
    BTI_WORD          dbHandle,  
    const BTI_CHAR*   user);
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>user</i>	Database user name

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified account or user name does not exist.
PCM_errNotAllowedToDropAdministrator	Attempt to drop Master user.
PCM_errDatabaseHasNoSecurity	Database has no security.
PCM_errSessionSecurityError	Database opened with insufficient privilege.

## Remarks

The following preconditions must be met:

- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.
- A user with the same name must already exist in the specified database.

---

The following post condition must be met:

- Use `PvCloseDatabase()` to free the resources.

## See Also

`PvAddUserToGroup()`

`PvAlterUserName()`

`PvAlterUserPassword()`

`PvCreateUser()`

`PvRemoveUserFromGroup()`

`PvOpenDatabase()`

`PvCloseDatabase()`



---

# PvFreeDbNamesData()

Free the resource allocated for database names on a connected server. This function needs to be called after preceding calls to PvGetDbNamesData.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvFreeDbNamesData(  
    BTI_LONG          hConnection);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
----	--------------------	--

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to database names not available.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- Database names data retrieved by calling [PvGetDbNamesData\(\)](#).

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbNamesData\(\)](#)

[PvGetDbName\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvFreeMkdeClientsData()

Free the cached information related to the active MicroKernel Engine clients. This function needs to be called after preceding calls to [PvGetMkdeClientsData](#).

Header File: [monitor.h](#) (See also [Header Files](#))

Function First Available In Library: [w3dbav75.dll](#) (Windows), [libpsqldti.so](#) (Linux), [libpsqldti.dylib](#) (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvFreeMkdeClientsData(  
    BTI_LONG      hConnection);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
----	--------------------	--

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_FAIL	Failed to disconnect to the named server.

---

### Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, [P\\_LOCAL\\_DB\\_CONNECTION](#) may be used as the connection handle.
- Data for active clients retrieved by calling [PvGetMkdeClientsData\(\)](#);

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeClientsData\(\)](#)

[PvGetMkdeClientInfo\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvFreeOpenFilesData()

Free the cached information related to the open files. This function needs to be called after preceding calls to PvGetOpenFilesData.

Header File: monitor.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvFreeOpenFilesData(  
    BTI_LONG      hConnection);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
----	--------------------	--

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_FAIL	Failed to disconnect to the named server.

---

### Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- Data for open files retrieved by calling [PvGetOpenFilesData\(\)](#).

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetOpenFilesData\(\)](#)

[PvGetOpenFileName\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvFreeSQLConnectionsData()

Free the cached information related to SQL connections. This function needs to be called after preceding calls to `PvGetSQLConnectionsData`.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvFreeSQLConnectionsData(  
    BTI_LONG hConnection);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <code>PvConnectServer()</code> function.
----	--------------------	---

---

### Return Values

---

<code>P_OK</code>	The operation was successful.
<code>P_E_INVALID_HANDLE</code>	Invalid connection handle.
<code>P_E_DATA_UNAVAILABLE</code>	Data related to active clients not available.
<code>P_E_FAIL</code>	Failed to disconnect to the named server.

---

### Remarks

The following preconditions must be met:

- Connection established by `PvConnectServer()` or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- Data for open files retrieved by calling `PvGetSQLConnectionsData()`.

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetSQLConnectionsData\(\)](#)

[PvGetSQLConnectionInfo\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

# PvFreeTable()

Frees memory allocated by a [PvGetTable\(\)](#) function call.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
RESULT PvFreeTable(  
    TABLEINFO*   tableProps,  
    COLUMNMAP*    columnList,  
    INDEXMAP*     indexList);
```

## Arguments

In/Out	<i>tableProps</i>	Pointer to a structure containing table information
In/Out	<i>columnList</i>	Pointer to an array of columns defined in the table.
In/Out	<i>indexList</i>	Pointer to an array of segments defined in the table.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	A general failure occurred

## Remarks

This function frees the structures created during a [PvGetTable\(\)](#) call.

## Example

```
RESULT status = 0;  
status = PvFreeTable(mytableProps, MyColumnList MyindexList);
```

---

## See Also

PvStart()

PvOpenDatabase()

PvGetTableNames()

PvGetTable()

PvFreeTableNames()

PvCloseDictionary()

PvStop()

---

# PvFreeTableNames()

Frees memory allocated with a [PvGetTableNames\(\)](#) call.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
PRELST PvFreeTableNames(  
    TABLEMAP*    tableList);
```

## Arguments

---

In/Out	<i>tableList</i>	Array of <code>TABLEMAP</code> structures that contain table names.
--------	------------------	---

---

## Return Values

---

<code>PCM_Success</code>	The operation was successful.
<code>PCM_errFailed</code>	The operation was not successful.

---

## Remarks

The memory freed with this function is successfully allocated during a [PvGetTableNames\(\)](#) call to retrieve all of the table names for a specified dictionary.

## Example

```
PRELST status = 0;  
status = PvFreeTableNames(&mytableList);
```

## See Also

[PvStart\(\)](#)  
[PvOpenDatabase\(\)](#)  
[PvGetTableNames\(\)](#)  
[PvGetTable\(\)](#)

---

PvFreeTable()  
PvCloseDictionary()  
PvStop()

---

# PvGetAllPossibleSelections()

Retrieves all available selection choices for a setting of types (PVSETTING\_SINGLE\_SEL or PVSETTING\_MULTI\_SEL).

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetAllPossibleSelections(  
    BTI_LONG          hConnection,  
    BTI_ULONG        settingID,  
    BTI_ULONG_PTR    pNumItems,  
    BTI_ULONG_PTR    pSelectionList);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pNumItems</i>	Address of an unsigned long that receives the total number of selection items. You can also retrieve the number of selection items by calling <a href="#">PvCountSelectionItems()</a>
Out	<i>pSelectionList</i>	Array that contains all available selection choices.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_INVALID_DATA_TYPE	The requested setting is not of selection type.
P_E_BUFFER_TOO_SMALL	The array size is too small. In this case, the required size is returned in <i>pNumItems</i> .
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvCountSelectionItems\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetBooleanStrings()

Retrieves display string related to Boolean type setting.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetBooleanStrings(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_LONG_PTR     trueStringSize,  
    BTI_CHAR_PTR      trueString,  
    BTI_LONG_PTR     falseStringSize,  
    BTI_CHAR_PTR      falseString);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>trueStringSize</i>	Long integer containing the length of <i>trueString</i> .
Out	<i>trueString</i>	Display string for TRUE (size >= 16 bytes).
Out	<i>falseStringSize</i>	Long integer containing the length of <i>falseString</i> .
Out	<i>falseString</i>	Display string for FALSE (size >= 16 bytes).

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The requested setting is not of long type.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

# PvGetBooleanValue()

Retrieves the value for a Boolean type setting. Either default or current value can be retrieved.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetBooleanValue(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_SINT_PTR      pValue,  
    BTI_SINT          whichData);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pValue</i>	Address of a Boolean variable that receives the setting value.
In	<i>whichData</i>	Flag to indicate which value is requested: PVDATA_DEFAULT returns default value. PVDATA_CURRENT returns current value

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_INVALID_DATA_TYPE	The requested setting is not of Boolean type.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetBooleanStrings\(\)](#)

[PvSetBooleanValue\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetCategoryInfo()

Retrieves information about a category of engine settings.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetCategoryInfo(  
    BTI_LONG      hConnection,  
    BTI_ULONG     categoryID,  
    PVCATEGORYINFO* pCatInfo);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>categoryID</i>	Unique identifier for the category. You can obtain a list of identifiers via the <a href="#">PvGetCategoryList()</a> function.
Out	<i>pCatInfo</i>	Address of a <a href="#">PVCATEGORYINFO</a> structure that will receive the category information.

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

The number of settings returned in the [PVCATEGORYINFO](#) structure represents the total number of settings for that category, both client and server. To get the applicable number of settings, call [PvGetSettingList\(\)](#). If it is a remote connection, the server side settings are not applicable.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetCategoryList()

Retrieves the list of category IDs on the engine specified by the current connection.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetCategoryList(  
    BTI_LONG          hConnection,  
    BTI_ULONG_PTR    pnumCategories,  
    BTI_ULONG_PTR    pCategoriesList);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In/Out	<i>pnumCategories</i>	Address of an unsigned long containing the number of categories that can be returned in <i>pCategoriesList</i> . You can also call <a href="#">PvGetCategoryListCount()</a> to retrieve this value.
Out	<i>pCategoriesList</i>	Array containing the category IDs.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_FAIL	Failed for other reasons.
P_E_BUFFER_TOO_SMALL	Array size is too small. The required size is returned in <i>pnumCategories</i> .

### Remarks

The following precondition must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryInfo\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetCategoryListCount()

Retrieves the number of categories on the engine specified by the current connection. This number can then be used to allocate an array to pass to [PvGetCategoryList\(\)](#).

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetCategoryListCount(  
    BTI_LONG      hConnection,  
    BTI_ULONG_PTR pListCount);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pListCount</i>	Address of an unsigned long containing the number of categories.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_FAIL	Failed for other reasons.

### Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

---

## See Also

PvStart()

PvConnectServer()

PvGetCategoryInfo()

PvDisconnect()

PvStop()



---

# PvGetDbCodePage()

Retrieves the code page associated with a named database.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvGetDbCodePage(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  dbName,  
    BTI_LONG_PTR  pDbCodePage);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database. A list of all database names for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single database name from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
Out	<i>pDbCodePage</i>	Code page of the database. A value of zero indicates the default code page on the server.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_NOT_EXIST	Named database does not exist.
P_E_FAIL	Failed for other reasons.

## Remarks

The following precondition must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvConnectServer\(\)](#)

[PvCreateDatabase2\(\)](#)

[PvCreateDSN2\(\)](#)

[PvModifyDatabase2\(\)](#)

[PvModifyDSN2\(\)](#)

[PvGetDSNEx2\(\)](#)

[PvStart\(\)](#)

---

## PvGetDbDataPath()

Retrieves the data path (where data files reside) of a named database. This information is stored in `dbnames.cfg`.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvGetDbDataPath(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbName,  
    BTI_ULONG_PTR    pBufSize,  
    BTI_CHAR_PTR     dataPath);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database. A list of all database names for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single database name from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer. Receives actual size of the path returned.
Out	<i>dataPath</i>	Contains the data path if successful, or empty string otherwise.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in <i>pBufSize</i> .
P_E_NOT_EXIST	Named database does not exist.

---

---

P\_E\_FAIL

Failed for other reasons.

---

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbNamesData\(\)](#)

[PvGetDbName\(\)](#)

[PvGetDbDictionaryPath\(\)](#)

[PvGetDbServerName\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetDbDictionaryPath()

Retrieves the dictionary path (where DDF files reside) of a named database.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libsqldti.so (Linux), libsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvGetDbDictionaryPath(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_ULONG_PTR     pBufSize,  
    BTI_CHAR_PTR      dictPath);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database. A list of all database names for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single database name from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer. Receives actual size of the path returned.
Out	<i>dictPath</i>	Contains the dictionary path if successful, or empty string otherwise.

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in <i>pBufSize</i> .
P_E_NOT_EXIST	Named database does not exist.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbNamesData\(\)](#)

[PvGetDbName\(\)](#)

[PvGetDbDataPath\(\)](#)

[PvGetDbServerName\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetDbFlags()

Retrieves the database flags associated with a named database.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libsqldti.so (Linux), libsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvGetDbFlags(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbName,  
    BTI_ULONG_PTR    pDbFlags);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database. A list of all database names for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single database name from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
Out	<i>pDbFlags</i>	Database flags, which can be a combination of the P_DBFLAG_ constants. <ul style="list-style-type: none"><li>• P_DBFLAG_RI (integrity constraints, including referential integrity and triggers)</li><li>• P_DBFLAG_BOUND (DDF files stamped with the database name so only that database can use them)</li><li>• P_DBFLAG_DBSEC_AUTHENTICATION (Mixed security policy. See <a href="#">Btrieve Security Policy</a>.)</li><li>• P_DBFLAG_DBSEC_AUTHORIZATION (Database security policy. See <a href="#">Btrieve Security Policy</a>.)</li><li>• P_DBFLAG_LONGMETADATA (see <a href="#">Metadata Version</a>)</li></ul>

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer

---

---

P_E_NOT_EXIST	Named database does not exist.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## Retrieve Security Policy

The following table indicates how to interpret the security model of an existing database.

This Flag Combination	Represent This Security Model
No flags	Classic
P_DBFLAG_DBSEC_AUTHENTICATION	Mixed
P_DBFLAG_DBSEC_AUTHENTICATION + P_DBFLAG_DBSEC_AUTHORIZATION	Database

---

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvCreateDatabase\(\)](#)  
[PvModifyDatabase\(\)](#)  
[PvGetDbNamesData\(\)](#)  
[PvGetDbName\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)



---

## PvGetDbName()

Gets the name of a database on a connected server using a sequence number. You can obtain the number of database names by calling the [PvGetDbNamesData\(\)](#) function. The sequence number is 1 based.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvGetDbName(  
    BTI_LONG          hConnection,  
    BTI_ULONG        sequence,  
    BTI_ULONG_PTR    pBufSize,  
    BTI_CHAR_PTR     dbName);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>sequence</i>	The sequence number (1 based) of the database name. Must be within a valid range with upper limit defined by <a href="#">PvGetDbNamesData()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of buffer allocated to receive the database name. Receives actual size of chars copied. The size should include the null terminator.
Out	<i>dbName</i>	String value returned.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to database names not available.
P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	Allocated buffer is too small for the string.
P_E_INVALID_SEQUENCE	Sequence number is not valid.

---

---

P\_E\_FAIL

Failed for other reasons.

---

## Example

```
BTI_ULONG i;
BTI_ULONG count = 0;
BTI_CHAR dbName[BDB_SIZE_DBNAME+1];
BTI_SINT status = PvGetDbNamesData(connection, &count);
for (i=1; i<= count; i++)
{
    BTI_ULONG dbNameSize = sizeof(dbName);
    status = PvGetDbName(connection, i, &dbNameSize, dbName);
}
status = PvFreeDbNamesData(connection);
```

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- Database names data retrieved by calling [PvGetDbNamesData\(\)](#)
- Caller has a valid database name sequence number.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbNamesData\(\)](#)

[PvFreeDbNamesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetDbNamesData()

Retrieves the number of database names for a connected server. Use the [PvGetDbName\(\)](#) function to enumerate the names.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvGetDbNamesData(  
    BTI_LONG          hConnection,  
    BTI_ULONG_PTR    pCount);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pCount</i>	Address of an unsigned long to receive the number of database names on the server.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

### Remarks

The following precondition must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

---

This function should be called first before calling any other functions to get database names information. The caller should call [PvFreeDbNamesData\(\)](#) to free the resources allocated for database names.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbName\(\)](#)

[PvFreeDbNamesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetDbServerName()

Retrieves the name of the server where the named database resides.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvGetDbServerName(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_ULONG_PTR     pBufferSize,  
    BTI_CHAR_PTR      serverName,  
    BTI_SINT_PTR      pIsLocal);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database. A list of all database names for a particular server is obtained with the <a href="#">PvGetDbNamesData()</a> function. A single database name from the resulting list can be obtained with the <a href="#">PvGetDbName()</a> function.
In/Out	<i>pBufferSize</i>	Address of an unsigned long containing the size of the buffer. Actual size of server name is returned.
Out	<i>serverName</i>	Contains server name if successful, empty string otherwise.
Out	<i>pIsLocal</i>	Returns zero for remote server, non-zero for local server.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in <i>pBufferSize</i> .
P_E_NOT_EXIST	Named database does not exist.

---

---

P\_E\_FAIL

Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbNamesData\(\)](#)

[PvGetDbName\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetDSN()

Retrieves information about the datasource name (DSN).

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

## Syntax

```
BTI_API PvGetDSN(  
    BTI_LONG           hConnection,  
    BTI_CHAR_PTR      dsnName,  
    BTI_ULONG_PTR     pdsnDescSize,  
    BTI_CHAR_PTR      dsnDesc,  
    BTI_ULONG_PTR     pdsnDBQSize,  
    BTI_CHAR_PTR      dsnDBQ);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dsnName</i>	Name of the datasource. A list of DSNs can be obtained with the <a href="#">PvListDSNs()</a> function.
In/Out	<i>pdsnDescSize</i>	Address of an unsigned long containing size of the buffer for DSN description. Receives actual size of DSN description.
Out	<i>dsnDesc</i>	Contains the description of DSN if successful.
In/Out	<i>pdsnDBQSize</i>	Address of an unsigned long containing size of the buffer for name of database. Receives actual size of database name.
Out	<i>dsnDBQ</i>	Contains the name of the database if successful.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.

---

P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in pdsnDescSize or pdsnDBQSize.
P_E_FAIL	Failed to retrieve data path.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

To retrieve information about a DSN without having to prompt the user to login, pass empty strings for username and password when establishing the server connection with [PvConnectServer\(\)](#).

**Note:** The connection established by passing empty strings for username and password is an insecure connection, and will not have sufficient rights to perform most of the other operations in DTI.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetDSNEx\(\)](#)  
[PvListDSNs\(\)](#)  
[PvCountDSNs\(\)](#)  
[PvCreateDSN\(\)](#)  
[PvModifyDSN\(\)](#)  
[PvDeleteDSN\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)



---

## PvGetDSNEx()

Retrieves information about the datasource name (DSN). This function is identical to [PvGetDSN\(\)](#) except that the DSN open mode is also retrieved.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

### Syntax

```
BTI_API PvGetDSNEx(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dsnName,  
    BTI_ULONG_PTR    pdsnDescSize,  
    BTI_CHAR_PTR     dsnDesc,  
    BTI_ULONG_PTR    pdsnDBQSize,  
    BTI_CHAR_PTR     dsnDBQ,  
    BTI_LONG_PTR     pOpenMode);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dsnName</i>	Name of the datasource. A list of DSNs can be obtained with the <a href="#">PvListDSNs()</a> function.
In/Out	<i>pdsnDescSize</i>	Address of an unsigned long containing size of the buffer for DSN description. Receives actual size of DSN description.
Out	<i>dsnDesc</i>	Contains the description of DSN if successful.
In/Out	<i>pdsnDBQSize</i>	Address of an unsigned long containing size of the buffer for name of database. Receives actual size of database name.
Out	<i>dsnDBQ</i>	Contains the name of the database if successful.

---

Out	<i>pOpenMode</i>	Contains open mode of DSN, which is one of the following: <ul style="list-style-type: none"> <li>NORMAL_MODE</li> <li>ACCELERATED_MODE,</li> <li>READONLY_MODE</li> <li>EXCLUSIVE_MODE</li> </ul> See also <a href="#">DSN Open Mode</a> in <i>ODBC Guide</i> .
-----	------------------	---

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in <i>pdsnDescSize</i> or <i>pdsnDBQSize</i> .
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_DSN_DOES_NOT_EXIST	The specified DSN does not exist.
P_E_INVALID_OPEN_MODE	Invalid open mode.
P_E_FAIL	Failed to retrieve data path.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, *P\_LOCAL\_DB\_CONNECTION* may be used as the connection handle.

To retrieve information about a DSN without having to prompt the user to login, pass empty strings for username and password when establishing the server connection with [PvConnectServer\(\)](#).

**Note:** The connection established by passing empty strings for username and password is an insecure connection, and will not have sufficient rights to perform most of the other operations in DTI.

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvListDSNs\(\)](#)

[PvCountDSNs\(\)](#)

[PvGetDSN\(\)](#)

[PvCreateDSN\(\)](#)

[PvModifyDSN\(\)](#)

[PvDeleteDSN\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetDSNEx2()

Retrieves information about the data source name (DSN). This function is the same as [PvGetDSNEx\(\)](#) except that the encoding option for data is also retrieved.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

### Syntax

```
BTI_API PvGetDSNEx2(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dsnName,  
    BTI_ULONG_PTR    pdsnDescSize,  
    BTI_CHAR_PTR     dsnDesc,  
    BTI_ULONG_PTR    pdsnDBQSize,  
    BTI_CHAR_PTR     dsnDBQ,  
    BTI_LONG_PTR     pOpenMode,  
    BTI_LONG_PTR     translate);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dsnName</i>	Name of the datasource. A list of DSNs can be obtained with the <a href="#">PvListDSNs()</a> function.
In/Out	<i>pdsnDescSize</i>	Address of an unsigned long containing size of the buffer for DSN description. Receives actual size of DSN description.
Out	<i>dsnDesc</i>	Contains the description of DSN if successful.
In/Out	<i>pdsnDBQSize</i>	Address of an unsigned long containing size of the buffer for name of database. Receives actual size of database name.
Out	<i>dsnDBQ</i>	Contains the name of the database if successful.

---

Out	<i>pOpenMode</i>	Open mode for the DSN, which is one of the following: <ul style="list-style-type: none"> <li>NORMAL_MODE</li> <li>ACCELERATED_MODE</li> <li>READONLY_MODE</li> <li>EXCLUSIVE_MODE</li> </ul> See also <a href="#">DSN Open Mode</a> in <i>ODBC Guide</i> .
Out	<i>translate</i>	Encoding option for data, which can be one of the following: <ul style="list-style-type: none"> <li>DSNFLAG_DEFAULT</li> <li>DSNFLAG_OEMANSI</li> <li>DSNFLAG_AUTO</li> </ul> See also <a href="#">DSN Open Mode</a> in <i>ODBC Guide</i> . Note that DSNFLAG_DEFAULT corresponds to the "None" encoding option in ODBC Administrator.

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in pdsnDescSize or pdsnDBQSize.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_DSN_DOES_NOT_EXIST	The specified DSN does not exist.
P_E_INVALID_OPEN_MODE	Invalid open mode.
P_E_INVALID_TRANSLATE_OPTION	The specified encoding translation option is invalid.
P_E_FAIL	Failed to retrieve data path.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

To retrieve information about a DSN without having to prompt the user to login, pass empty strings for username and password when establishing the server connection with `PvConnectServer()`.

**Note:** The connection established by passing empty strings for username and password is an insecure connection, and will not have sufficient rights to perform most of the other operations in DTI.

## See Also

- `PvConnectServer()`
- `PvCountDSNs()`
- `PvCreateDSN2()`
- `PvDeleteDSN()`
- `PvDisconnect()`
- `PvGetDSNEx()`
- `PvListDSNs()`
- `PvModifyDSN2()`
- `PvStart()`
- `PvStop()`

---

# PvGetEngineInformation()

Retrieves the information about the database engine for a given *hConnection*.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvGetEngineInformation(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     pserverClient,  
    BTI_ULONG_PTR    pdbuApiVer,  
    BTI_ULONG_PTR    pmajor,  
    BTI_ULONG_PTR    pminor,  
    BTI_ULONG_PTR    pserverClientType);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pserverClient</i>	Address of a BTI_CHAR_PTR True - MKDE_SERVER_ENGINE_CID False - MKDE_CLNT_ENGINE_CID
Out	<i>pdbuApiVer</i>	Version of the structures. Can be NULL
Out	<i>pmajor</i>	Major version - can be NULL.
Out	<i>pminor</i>	Minor version - can be NULL.
Out	<i>pserverClientType</i>	Only for MKDE_SRVR_ENGINE_CID. Returns one of the following: UNKNOWN_ENGINE_CLIENT (0) NT_SERVER (1) WIN32_CLIENT (3) UNIX_SERVER (4) CLIENT_CACHE (5) VXWIN_SERVER(6) VXLINUX_SERVER(7) REPORT_ENGINE(9)

---

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_FAIL	Failed for other reasons.

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

## PvGetError()

Returns an error description string, describing the preceding error. This function is only for errors encountered in catalog functions.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT PvGetError(  
    LPSTR      errorDesc,  
    WORD*     size);
```

### Arguments

In/Out	<i>errorDesc</i>	String that will contain the error description.
In/Out	<i>size</i>	Size of <i>errorDesc</i> . If the size is not large enough to contain the error description, an error is returned and the required size is contained in <i>size</i> .

### Return Values

PCM_Success	The operation was successful.
PCM_errStringTooShort	The <i>size</i> parameter was not large enough to contain the error description. The required length is returned in the <i>size</i> argument.

### Remarks

The *errorDesc* string is allocated by the caller.

The maximum size of the error description is specified in the constant `ERROR_LEN` found in the header file `ddf.h`.

---

## See Also

[PvStart\(\)](#)

[PvStop\(\)](#)

---

# PvGetFileHandlesData()

Retrieves all the file handle information related to an open file.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetFileHandlesData(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     fileName,  
    BTI_ULONG_PTR    pCount);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>fileName</i>	Full path name of the file to be queried.
Out	<i>pCount</i>	Address of an unsigned long to receive the number of handles for the open file.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FILE_NOT_OPEN	Specified file is not currently open.
P_E_FAIL	Failed to disconnect to the named server.

## Remarks

The information will be cached by DTI for subsequent calls related to file handles. This function would be called first for an open file before calling any other functions to get file handle

---

information. The cached information for the file handles will be freed when [PvFreeOpenFilesData\(\)](#) is called.

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- Data for open files retrieved by calling [PvGetOpenFilesData\(\)](#)
- Caller already has a valid open file name.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetOpenFilesData\(\)](#)

[PvFreeOpenFilesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetFileHandleInfo()

Query the information for a file handle associated with an open file.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetFileHandleInfo(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  fileName,  
    BTI_ULONG     sequence,  
    PVFILEHDLINFO* pFileHdlInfo);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>fileName</i>	Full path name of the file to be queried.
In	<i>sequence</i>	The sequence number (zero-based) of the file handle. Must be within a valid range with upper limit defined by the number of file handles obtained by <a href="#">PvGetFileHandlesData()</a> .
Out	<i>pFileHdlInfo</i>	Address of a <a href="#">PVFILEHDLINFO</a> structure to receive the information on the file handle.

## Return Values

<code>P_OK</code>	The operation was successful.
<code>P_E_INVALID_HANDLE</code>	Invalid connection handle.
<code>P_E_DATA_UNAVAILABLE</code>	Data related to active clients not available.
<code>P_E_NULL_PTR</code>	Call with NULL pointer
<code>P_E_INVALID_SEQUENCE</code>	Sequence number is not valid
<code>P_E_FILE_NOT_OPEN</code>	Specified file is not currently open.
<code>P_E_FAIL</code>	Failed to disconnect to the named server.

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- Data for open files retrieved by calling [PvGetOpenFilesData\(\)](#)
- Data for open file handles retrieved by calling [PvGetFileHandlesData\(\)](#);
- Caller already has a valid open file name.
- Caller already has a valid file handle sequence.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetOpenFilesData\(\)](#)

[PvGetFileHandlesData\(\)](#)

[PvGetOpenFileName\(\)](#)

[PvFreeOpenFilesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetFileInfo()

Query the information for an open file.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetFileInfo(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  fileName,  
    PVFILEINFO*   pFileInfo);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>fileName</i>	Full path name of the file to be queried.
Out	<i>pFileInfo</i>	Address of a <a href="#">PVFILEINFO</a> structure to receive the information on the file.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_NULL_PTR	Call with NULL pointer
P_E_FILE_NOT_OPEN	Specified file is not currently open.
P_E_FAIL	Failed for other reasons.

## Remarks

The following preconditions must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
  - Data for open files retrieved by calling [PvGetOpenFilesData\(\)](#);
  - Caller already has a valid open file name.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetOpenFilesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

# PvGetLongValue()

Retrieves the value for a long integer type setting, from the data source specified by *whichData*.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetLongValue(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID,  
    BTI_LONG_PTR  pValue,  
    BTI_SINT      whichData);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pValue</i>	Address of a long integer variable that receives the setting value.
In	<i>whichData</i>	Flag to indicate which value is requested: PVDATA_DEFAULT returns default value. PVDATA_CURRENT returns current value

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_INVALID_DATA_TYPE	The requested setting is not of long integer type.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

To obtain the minimum and maximum values that the setting can accept, use the [PvGetValueLimit\(\)](#) function.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetValueLimit\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetMkdeClientId()

Get the client ID of an active MicroKernel Engine client.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeClientId(  
    BTI_LONG      hConnection,  
    BTI_ULONG     sequence,  
    PVCLIENTID*  pClientId);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>sequence</i>	The sequence number (zero based) of the MicroKernel Engine client. Must be within a valid range with upper limit returned by <a href="#">PvGetMkdeClientsData()</a> .
Out	<i>pClientId</i>	Address of the <a href="#">PVCLIENTID</a> structure to hold the returned client ID information.

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_SEQUENCE	Sequence number is not valid.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- 
- DTI session started by calling [PvStart\(\)](#).
  - Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
  - Data for active clients retrieved by calling [PvGetMkdeClientsData\(\)](#)

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeClientsData\(\)](#)

[PvGetMkdeClientInfo\(\)](#)

[PvFreeMkdeClientsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetMkdeClientInfo()

Query the information for an active MicroKernel Engine client.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeClientInfo(  
    BTI_LONG          hConnection,  
    PVCLIENTID*      pClientId,  
    PVMKDECLIENTINFO* pClientInfo);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pClientId</i>	Address of the <a href="#">PVCLIENTID</a> structure to identify the MicroKernel Engine client.
Out	<i>PClientInfo</i>	Address of a <a href="#">PVMKDECLIENTINFO</a> structure to receive the information for the MicroKernel Engine client.

## Return Values

<code>P_OK</code>	The operation was successful.
<code>P_E_INVALID_HANDLE</code>	Invalid connection handle.
<code>P_E_DATA_UNAVAILABLE</code>	Data related to active clients not available.
<code>P_E_NULL_PTR</code>	Call with NULL pointer.
<code>P_E_INVALID_CLIENT</code>	Invalid client ID.
<code>P_E_FAIL</code>	Failed for other reasons.

## Remarks

The following preconditions must be met:

- 
- DTI session started by calling [PvStart\(\)](#).
  - Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
  - Data for active clients retrieved by calling [PvGetMkdeClientsData\(\)](#).
  - Caller already has a valid active MicroKernel Engine client ID.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeClientsData\(\)](#)

[PvGetMkdeClientId\(\)](#)

[PvFreeMkdeClientsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetMkdeClientHandlesData()

Retrieves the number of MicroKernel Engine client handles related to an active client.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeClientHandlesData(  
    BTI_LONG          hConnection,  
    PVCLIENTID*     pClientId,  
    BTI_ULONG_PTR    pCount);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pClientId</i>	Address of the <a href="#">PVCLIENTID</a> structure to identify the MicroKernel Engine client.
Out	<i>pCount</i>	Address of an unsigned long to receive the number of handles for the MicroKernel Engine client.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to MicroKernel Engine clients not available.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

## Remarks

When you call this function, all information regarding MicroKernel Engine client handles is cached by DTI for subsequent function calls related to client handles. If you want to obtain other information about clients, see [PvGetMkdeClientsData\(\)](#).

---

This function should be called first before calling any other functions that return client handle information.

The cached information for the MicroKernel Engine client handles will be freed along with the information about the clients when [PvFreeMkdeClientsData\(\)](#) is called.

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- Data for active clients retrieved by calling [PvGetMkdeClientsData\(\)](#).
- Caller already has a valid active MicroKernel Engine client ID.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeClientsData\(\)](#)

[PvFreeMkdeClientsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

# PvGetMkdeClientHandleInfo()

Query the information for a MicroKernel Engine client handle associated with an active client.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeClientHandleInfo(  
    BTI_LONG          hConnection,  
    PVCLIENTID*      pClientId,  
    BTI_ULONG         sequence,  
    PVMKDECLIENTHDLINFO* pClientHdlInfo);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pClientId</i>	Address of the <a href="#">PVCLIENTID</a> structure to identify the MicroKernel Engine client.
In	<i>sequence</i>	The sequence number (zero based) of the client handle. Must be within a valid range with upper limit defined by the number of handles obtained by <a href="#">PvGetMkdeClientHandlesData()</a> .
Out	<i>pClientHdlInfo</i>	Address of a <a href="#">PVMKDECLIENTHDLINFO</a> structure to receive the information on the client handle.

---

## Return Values

---

<code>P_OK</code>	The operation was successful.
<code>P_E_NULL_PTR</code>	Call with NULL pointer.
<code>P_E_INVALID_HANDLE</code>	Invalid connection handle.
<code>P_E_INVALID_CLIENT</code>	Invalid client ID.
<code>P_E_INVALID_SEQUENCE</code>	Sequence number is not valid.
<code>P_E_FAIL</code>	Failed to disconnect to the named server.
<code>P_E_DATA_UNAVAILABLE</code>	Data related to active clients not available.

---

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- Data for active MicroKernel Engine clients retrieved by calling [PvGetMkdeClientsData\(\)](#);
- Data for MicroKernel Engine client handles retrieved by calling [PvGetMkdeClientHandlesData\(\)](#);
- Caller already has a valid active MicroKernel Engine client ID.
- Caller already has a valid handle sequence for the active MicroKernel Engine client.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeClientsData\(\)](#)

[PvGetMkdeClientHandlesData\(\)](#)

[PvFreeMkdeClientsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetMkdeClientsData()

Retrieves all the information related to the active MicroKernel Engine clients.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeClientsData(  
    BTI_LONG      hConnection,  
    BTI_ULONG_PTR pCount);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pCount</i>	Address of an unsigned long to receive the number of active MicroKernel Engine clients.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

## Remarks

When you call this function, all information regarding MicroKernel Engine clients is cached by DTI for subsequent function calls related to clients. The one exception is information regarding client handles, which is cached using a similar function [PvGetMkdeClientHandlesData\(\)](#).

This function should be called first before calling any other functions that return client information. The caller should call [PvFreeMkdeClientsData\(\)](#) to free the cached information when it is no longer needed.

---

This function can also be called to refresh the cached information.

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvFreeMkdeClientsData\(\)](#)

[PvGetMkdeClientHandlesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetMkdeCommStat()

Retrieves all the MicroKernel Engine communication statistics data.

Header File: monitor.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetMkdeCommStat(  
    BTI_LONG      hConnection,  
    PVCMMSTAT*   pCommStat);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pCommStat</i>	Address of a <a href="#">PVCMMSTAT</a> structure to receive the MicroKernel Engine communication statistics.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_COMPONENT_NOT_LOADED	Component is not loaded
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed to disconnect to the named server.

### Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, [P\\_LOCAL\\_DB\\_CONNECTION](#) may be used as the connection handle.
- Data for open files retrieved by calling [PvGetSQLConnectionsData\(\)](#)

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetSQLConnectionsData\(\)](#)

[PvGetMkdeUsage\(\)](#)

[PvFreeSQLConnectionsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetMkdeCommStatEx()

Retrieves all the MicroKernel Engine communication statistics data.

Header File: monitor.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeCommStatEx(  
    BTI_LONG hConnection,  
    PVCOMMSTATEX* pCommStatEx);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pCommStatEx</i>	Address of a <a href="#">PVCOMMSTATEX</a> structure to receive the MicroKernel Engine communication statistics.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_COMPONENT_NOT_LOADED	Component is not loaded
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed to disconnect to the named server.

## Remarks

This function returns the same data as [PvGetMkdeCommStat](#) but uses a new structure [PVCOMMSTATEX](#) that contains two additional elements. The added elements ([totalTimeouts](#) and [totalRecoveries](#)) are related to the auto reconnect feature. See *Advanced Operations Guide* for more information on auto reconnect.

The following preconditions must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
  - Data for open files retrieved by calling [PvGetSQLConnectionsData\(\)](#)

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetSQLConnectionsData\(\)](#)

[PvGetMkdeUsage\(\)](#)

[PvFreeSQLConnectionsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

## PvGetMkdeUsage()

Retrieves the resource usage information from the MicroKernel Engine, including current, peak, and maximum settings for licenses, files, handles, transactions, clients, threads, and locks.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetMkdeUsage(  
    BTI_LONG      hConnection,  
    PVMKDEUSAGE* pMkdeUsage);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pMkdeUsage</i>	Address of a <a href="#">PVMKDEUSAGE</a> structure to receive the MicroKernel Engine resource usage information.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

### Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

---

## See Also

PvStart()

PvConnectServer()

PvGetMkdeCommStat()

PvGetMkdeUsageEx()

PvDisconnect()

PvStop()

---

## PvGetMkdeUsageEx()

Retrieves the resource usage information from the MicroKernel Engine database engine, including current, peak, and maximum settings for use count, session count, data in use, files, handles, transactions, clients, threads, and locks, and the duration, in seconds, that the database engine has been running (referred to as "engine uptime").

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetMkdeUsageEx(  
    BTI_LONG hConnection,  
    PVMKDEUSAGEEX* pMkdeUsage);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pMkdeUsage</i>	Address of a <a href="#">PVMKDEUSAGEEX</a> structure to receive the MicroKernel Engine resource usage information.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

### Remarks

This function, `PvGetMkdeUsageEx()`, is similar to [PvGetMkdeUsage\(\)](#); the only difference is in the structures. While supplying the same elements, [PVMKDEUSAGEEX](#) supplies four-byte elements when [PVMKDEUSAGE](#) supplies two-byte ones.

The following preconditions must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeCommStat\(\)](#)

[PvGetMkdeUsage\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetMkdeVersion()

Retrieves the MicroKernel Engine version information.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetMkdeVersion(  
    BTI_LONG      hConnection,  
    PVVERSION*   pMkdeVersion);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pMkdeVersion</i>	Address of a <a href="#">PVVERSION</a> structure to receive the MicroKernel Engine version information.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_COMPONENT_NOT_LOADED	Component not loaded.
P_E_FAIL	Failed for other reasons.

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

---

## See Also

PvStart()

PvConnectServer()

PvGetMkdeCommStat()

PvGetMkdeUsageEx()

PvDisconnect()

PvStop()

---

# PvGetOpenFilesData()

Retrieves all the information related to the open files.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetOpenFilesData(  
    BTI_LONG      hConnection,  
    BTI_ULONG_PTR pCount);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pCount</i>	Address of an unsigned long to receive the number of open files.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

## Remarks

The information will be cached by DTI for subsequent calls related to open files. This function should be called first before calling any other functions to get open file information.

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

The following post condition must be met:

- 
- The caller should call [PvFreeOpenFilesData\(\)](#) to free the cached information when it is no longer needed.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetOpenFileName\(\)](#)

[PvFreeOpenFilesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

# PvGetOpenFileName()

Retrieves the full path name of an open file.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetOpenFileName(  
    BTI_LONG          hConnection,  
    BTI_ULONG         sequence,  
    BTI_ULONG_PTR     pBufSize,  
    BTI_CHAR_PTR      fileName);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>sequence</i>	The sequence number (zero based) of the file. Must be within a valid range with upper limit returned by <a href="#">PvGetOpenFilesData()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of buffer allocated to receive the file name. Receives actual size of chars copied. The size should include the null terminator.
In/Out	<i>fileName</i>	String value returned.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_DATA_UNAVAILABLE	Data related to active clients not available.
P_E_NULL_PTR	Call with NULL pointer.
P_E_BUFFER_TOO_SMALL	Allocated buffer is too small for the string, returned string is truncated. In this case the required size is in <code>pBufSize</code> .
P_E_INVALID_SEQUENCE	Sequence number is not valid.
P_E_FAIL	Failed to disconnect to the named server.

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- Data for open files retrieved by calling [PvGetOpenFilesData\(\)](#).

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetOpenFilesData\(\)](#)

[PvFreeOpenFilesData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetProductsInfo()

Retrieves xml string with information on all Zen products found by the License Manager.

Header File: dtlicense.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvGetProductsInfo (
    BTI_LONG          hConnection,
    BTI_CHAR_PTR      productInfo,
    BTI_ULONG_PTR     pBufSize);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>productInfo</i>	XML string returned with product information.
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer allocated to receive the string. It receives the actual length of selection string.

## Return Values

DBU_SUCCESS	The operation was successful.
P_E_FAIL	Failed for other reasons.
Status code pertaining to license administration or to authorization	See <i>Status Codes and Messages</i> for <a href="#">License Administrator Status Codes</a> and <a href="#">Authorization Status Codes</a> .

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

## Product Information Returned by PvGetProductsInfo()

Following is the document type definition (DTD) for the XML string returned by PvGetProductsInfo() and an explanation of its terms:

```
<!DOCTYPE products [  
<!ELEMENT products (product*)>  
<!ELEMENT product (name,id,licenses)>  
<!ELEMENT name (#PCDATA)>  
<!ELEMENT id (#PCDATA)>  
<!ELEMENT licenses (license*)>  
<!ELEMENT license  
(type,productCode*,productKey*,state*,feature*,edition*,maxUserCount*,maxSessionCount*,maxDataInUseGB*,platform*,sequence*,userCount*,sessionCount*,dataInUseGB*,timeStamp*,oemId*,application*,description*,isremovable*,gracePeriodEnd*)>  
<!ELEMENT type (#PCDATA)>  
<!ELEMENT productCode (#PCDATA)>  
<!ELEMENT productKey (#PCDATA)>  
<!ELEMENT state (#PCDATA)>  
<!ELEMENT feature (#PCDATA)>  
<!ELEMENT edition (#PCDATA)>  
<!ELEMENT maxUserCount (#PCDATA)>  
<!ELEMENT maxSessionCount (#PCDATA)>  
<!ELEMENT maxDataInUseGB (#PCDATA)>  
<!ELEMENT platform (#PCDATA)>  
<!ELEMENT sequence (#PCDATA)>  
<!ELEMENT userCount (#PCDATA)>  
<!ELEMENT sessionCount (#PCDATA)>  
<!ELEMENT dataInUseGB (#PCDATA)>  
<!ELEMENT timeStamp (#PCDATA)>  
<!ELEMENT oemId (#PCDATA)>  
<!ELEMENT application (#PCDATA)>  
<!ELEMENT description (#PCDATA)>  
<!ELEMENT isremovable (#PCDATA)>  
<!ELEMENT gracePeriodEnd (#PCDATA)>  
>]
```

products	A container for all products returned by PvGetProductsInfo().
product	A container for information about a single product.
name	The name of the product.
id	The Zen code for the product. Refer to the dtlicense header file for the list of product codes returned.
licenses	A container for all licenses that apply to the product.
license	A container for information about a single license.

---

---

type	The license type: 1: Permanent 2: Expiring license set at issue date 4: Expiring license applied at install time 7: User count increase
productCode	The Zen code for the product. See the dtlicense header file for the list of product codes returned.
productKey	The key used for product authorization. Can be empty if product authorization was not used.
state	The current state of the license: 0: Active 1: Expired 2: Disabled 3: Inactive 4: Failed validation
feature	Reserved.
edition	Reserved.
maxUserCount	Maximum concurrent users allowed. Zero indicates unlimited users on Zen Enterprise Server and Workgroup editions. Not applicable on Zen Cloud Server edition and always returns zero.
maxSessionCount	Maximum concurrent sessions allowed. Zero indicates unlimited sessions on the Zen Cloud Server edition. Not applicable on Zen Enterprise Server and Workgroup editions and always returns zero.
maxDatainUseGB	Maximum amount of data allowed to be used simultaneously, measured in gigabytes. Zero indicates unlimited amount of data on Zen Cloud Server edition. Not applicable on Zen Enterprise Server and Workgroup editions and always returns zero.

---

---

platform	The supported platforms: 0: ANY 1: WIN 2: WIN32 3: WIN64 4: LINUX 5: LINUX32 6: LINUX64 7: MAC 8: MAC32 9: MAC64
sequence	The license sequence number.
userCount	The number of users permitted by the license. -1 indicates unlimited number of users on Zen Enterprise Server and Workgroup editions. Not applicable on Zen Cloud Server edition and always returns zero.
sessionCount	The number of sessions permitted by the license. -1 indicates unlimited number of users on Zen Cloud Server editions. Not applicable on Zen Enterprise Server and Workgroup editions and always returns zero.
dataInUseGB	The amount of data in use permitted by the license, measured in gigabytes. -1 indicates unlimited data count size on Zen Cloud Server editions. Not applicable on Zen Enterprise Server and Workgroup editions and always returns zero.
timeStamp	For temporary keys, the expiration day represented as the number of days from January 1, 2000.
oemId	The vendor ID.
application	The vendor's application ID.
description	Reserved.
isremovable	The license key is removable: 0: Not removable 1: Removable
gracePeriodEnd	Number of days remaining before the engine is disabled for failing license validation. Empty if a failed-validation period is not applicable to this product. -1 if a failed-validation period is applicable but not in effect for this product.

---

---

## Example

```
<?xml version="1.0" encoding='UCS-4' ?>
<!DOCTYPE products [
<!ELEMENT products (product*)>
<!ELEMENT product (name,id,licenses)>
<!ELEMENT name (#PCDATA)>
<!ELEMENT id (#PCDATA)>
<!ELEMENT licenses (license*)>
<!ELEMENT license
(type,productCode*,productKey*,state*,feature*,edition*,maxUserCount*,maxSessionCount*,maxDataInUseGB*,platform*,sequence*,userCount*,sessionCount*,dataInUseGB*,timeStamp*,oemId*,application*,description*,isremovable*,gracePeriodEnd*)>
<!ELEMENT type (#PCDATA)>
<!ELEMENT productCode (#PCDATA)>
<!ELEMENT productKey (#PCDATA)>
<!ELEMENT state (#PCDATA)>
<!ELEMENT feature (#PCDATA)>
<!ELEMENT edition (#PCDATA)>
<!ELEMENT maxUserCount (#PCDATA)>
<!ELEMENT maxSessionCount (#PCDATA)>
<!ELEMENT maxDataInUseGB (#PCDATA)>
<!ELEMENT platform (#PCDATA)>
<!ELEMENT sequence (#PCDATA)>
<!ELEMENT userCount (#PCDATA)>
<!ELEMENT sessionCount (#PCDATA)>
<!ELEMENT dataInUseGB (#PCDATA)>
<!ELEMENT timeStamp (#PCDATA)>
<!ELEMENT oemId (#PCDATA)>
<!ELEMENT application (#PCDATA)>
<!ELEMENT description (#PCDATA)>
<!ELEMENT isremovable (#PCDATA)>
<!ELEMENT gracePeriodEnd (#PCDATA)>
]>
<products>
  <product>
    <name>DataExchange 5 Server: Real-Time Backup</name>
    <id>78</id>
    <licenses>
      <license>
        <type>1</type>
        <productCode>78</productCode>
        <productKey> ABCDE-55555-FGHIJ-55555-KLMNO-55555</productKey>
        <state>0</state>
        <feature>0</feature>
        <edition>0</edition>
        <maxUserCount>0</maxUserCount>
        <maxSessionCount>0</maxSessionCount>
        <maxDataInUseGB>0</maxDataInUseGB>
        <platform>2</platform>
        <sequence>0</sequence>
        <userCount>1</userCount>
        <sessionCount>0</sessionCount>
        <dataInUseGB>0</dataInUseGB>
        <timeStamp>0</timeStamp>
        <oemId>0</oemId>
        <application>0</application>
        <description></description>
        <isremovable>1</isremovable>
        <gracePeriodEnd>-1</gracePeriodEnd>
      </license>
    </licenses>
  </product>
</products>
```

```

<name>PSQL 12 Server</name>
<id>425</id>
<licenses>
  <license>
    <type>2</type>
    <productCode>425</productCode>
    <productKey></productKey>
    <state>0</state>
    <feature>0</feature>
    <edition>0</edition>
    <maxUserCount>0</maxUserCount>
    <maxSessionCount>0</maxSessionCount>
    <maxDataInUseGB>0</maxDataInUseGB>
    <platform>2</platform>
    <sequence>0</sequence>
    <userCount>10</userCount>
    <sessionCount>0</sessionCount>
    <dataInUseGB>0</dataInUseGB>
    <timeStamp>4489</timeStamp>
    <oemId>8</oemId>
    <application>604</application>
    <description></description>
    <isremovable>0</isremovable>
    <gracePeriodEnd></gracePeriodEnd>
  </license>
  <license>
    <type>4</type>
    <productCode>425</productCode>
    <productKey></productKey>
    <state>0</state>
    <feature>0</feature>
    <edition>0</edition>
    <maxUserCount>0</maxUserCount>
    <maxSessionCount>0</maxSessionCount>
    <maxDataInUseGB>0</maxDataInUseGB>
    <platform>1</platform>
    <sequence>11200</sequence>
    <userCount>20</userCount>
    <sessionCount>0</sessionCount>
    <dataInUseGB>0</dataInUseGB>
    <timeStamp>4429</timeStamp>
    <oemId>0</oemId>
    <application>1</application>
    <description></description>
    <isremovable>0</isremovable>
    <gracePeriodEnd></gracePeriodEnd>
  </license>
  <license>
    <type>1</type>
    <productCode>425</productCode>
    <productKey>ABCDE-55555-FGHIJ-55555-KLMNO-55555</productKey>
    <state>0</state>
    <feature>0</feature>
    <edition>0</edition>
    <maxUserCount>0</maxUserCount>
    <maxSessionCount>0</maxSessionCount>
    <maxDataInUseGB>0</maxDataInUseGB>
    <platform>2</platform>
    <sequence>0</sequence>
    <userCount>10</userCount>
    <sessionCount>0</sessionCount>
    <dataInUseGB>0</dataInUseGB>
    <timeStamp>0</timeStamp>
    <oemId>333</oemId>
    <application>334</application>

```



---

```
<description></description>
<isremovable>1</isremovable>
<gracePeriodEnd>-1</gracePeriodEnd>
</license>
</licenses>
</product>
</products>
```

## See Also

[PvValidateLicenses\(\)](#)

[PvConnectServer\(\)](#)

[PvStart\(\)](#)

[PvStop\(\)](#)

---

## PvGetSelectionString()

Retrieves display string for a specific choice of selection type setting.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSelectionString(  
    BTI_LONG          hConnection,  
    BTI_ULONG        settingID,  
    BTI_ULONG        selection,  
    BTI_ULONG_PTR    pBufSize,  
    BTI_CHAR_PTR     dispString);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In	<i>selection</i>	Selection choice index. PSelectionList returned from <a href="#">PvGetAllPossibleSelections()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer allocated to receive the string. It receives the actual length of selection string.
Out	<i>dispString</i>	Display string returned.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The requested setting is not of selection type.
P_E_BUFFER_TOO_SMALL	The array size is too small. In this case, the required size is returned in <i>pBufSize</i> .

---

---

P\_E\_FAIL

Failed for other reasons.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetSelectionStringSize\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetSelectionStringSize()

Retrieves size of buffer needed for successful PvGetSelectionString () call.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSelectionStringSize(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_ULONG_PTR     pBufSize);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer in <a href="#">PvGetSelectionString()</a> call allocated to receive the string. It receives the actual length of selection string.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The requested setting is not of selection type.
P_E_FAIL	Failed for other reasons.

### Remarks

The following precondition must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetSelectionValue()

Retrieves the value for a selection type setting, from the data source specified by *whichData*.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSelectionValue(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_ULONG_PTR     pNumItems,  
    BTI_LONG_PTR      pValue,  
    BTI_SINT          whichData);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pNumItems</i>	Address of an unsigned long that specifies the array size on input, and receives the number of individual selection items on return.
Out	<i>pValue</i>	Array of individual selection indexes.
In	<i>whichData</i>	Flag to indicate which value is requested: PVDATA_DEFAULT returns default value. PVDATA_CURRENT returns current value

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The requested setting is not of string type.

---

P_E_BUFFER_TOO_SMALL	The array size is too small. In this case, the required size is returned in <i>pNumItems</i> .
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetCategoryList\(\)](#)  
[PvGetSettingList\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvGetServerName()

Retrieves the name of the connected server indicated by the connection handle.

Header File: connect.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetServerName(  
    BTI_LONG          hConnection,  
    BTI_ULONG_PTR    pBufSize,  
    BTI_CHAR_PTR     serverName);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer allocated to receive server name.
In/Out	<i>serverName</i>	Returned server name if successful, empty string otherwise.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in PBufSize.
P_E_FAIL	Failed to connect to the named server.

### Remarks

The implementation should perform the necessary initializations when called the first time.

Multiple simultaneous connections are allowed.



---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetSettingHelp()

Retrieves help string related to setting.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSettingHelp(  
    BTI_ULONG      settingID,  
    BTI_ULONG_PTR  pBufSize,  
    BTI_CHAR_PTR   pHelpString);
```

### Arguments

In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of buffer allocated to receive setting value. Receives actual size of setting value. The size should include the NULL terminator.
Out	<i>pHelpString</i>	String value returned.

### Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.
P_E_BUFFER_TOO_SMALL	The buffer allocated is too small and the display string is truncated. In this case, the required buffer size is returned in <i>pBufSize</i> .
P_E_FAIL	Failed for other reasons.

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetSettingInfo\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetSettingHelpSize()

Retrieves help string related to setting.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetSettingHelpSize(  
    BTI_ULONG      settingID,  
    BTI_ULONG_PTR  pBufSize);
```

## Arguments

In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of buffer allocated to receive setting value. Receives actual size of setting value. The size should include the NULL terminator.

## Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetSettingInfo\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetSettingInfo()

Retrieves setting information for a setting.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetSettingInfo(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID,  
    PVSETTINGINFO* pSettingInfo);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pSettingInfo</i>	Address of a <a href="#">PVSETTINGINFO</a> structure that receives setting information.

## Return Values

<code>P_OK</code>	The operation was successful.
<code>P_E_INVALID_HANDLE</code>	Invalid connection handle.
<code>P_E_NULL_PTR</code>	Call with <code>NULL</code> pointer.
<code>P_E_FAIL</code>	Failed for other reasons.

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

---

## See Also

PvStart()

PvConnectServer()

PvGetCategoryList()

PvGetSettingList()

PvGetSettingHelp()

PvDisconnect()

PvStop()

---

## PvGetSettingList()

Retrieves a list of settings belonging to the specified category.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSettingList(  
    BTI_LONG      hConnection,  
    BTI_ULONG     categoryID,  
    BTI_ULONG_PTR pNumSettings,  
    BTI_ULONG_PTR pSettingList);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>categoryID</i>	Unique identifier for the category
Out	<i>pNumSettings</i>	Address of an unsigned long containing size of the array on input, and receives number of items in the returned list.
Out	<i>pSettingList</i>	Pointer to the list of returned setting IDs.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_BUFFER_TOO_SMALL	The array size is too small. In this case, the required size is returned in <i>pNumSettings</i> .
P_E_FAIL	Failed for other reasons.



---

## Remarks

If the connection is a remote connection, only server-side settings for the category are returned. If the connection is a local connection, both client-side and server-side settings for this category will be returned.

Use [PvIsSettingAvailable\(\)](#) to determine if the setting can be set at this time.

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvIsSettingAvailable\(\)](#)

[PvGetSettingHelp\(\)](#)

[PvGetSettingInfo\(\)](#)

[PvGetSettingMap\(\)](#)

[PvGetSettingUnits\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetSettingListCount()

Retrieves number of settings belonging to the specified category. This number can then be used to allocate an array to pass to [PvGetSettingList\(\)](#).

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSettingListCount(  
    BTI_LONG      hConnection,  
    BTI_ULONG     categoryID,  
    BTI_ULONG_PTR pNumSettings);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>categoryID</i>	Unique identifier for the category.
Out	<i>pNumSettings</i>	Address of an unsigned long containing size of the array on input, and receives number of items in the returned list.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

### Remarks

If the connection is a remote connection, only server-side settings for the category are returned. If the connection is a local connection, both client-side and server-side settings for this category will be returned.

Use [PvIsSettingAvailable\(\)](#) to determine if the setting can be set at this time.

---

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvIsSettingAvailable\(\)](#)

[PvGetSettingHelp\(\)](#)

[PvGetSettingInfo\(\)](#)

[PvGetSettingMap\(\)](#)

[PvGetSettingUnits\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetSettingMap()

Retrieves option ID and component ID for a setting.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSettingMap(  
    BTI_ULONG      settingID,  
    BTI_WORD_PTR   pComponentID,  
    BTI_WORD_PTR   pOptionID);
```

### Arguments

In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pComponentID</i>	Address of an unsigned short for Component.
Out	<i>pOptionID</i>	Address of an unsigned short for Option

### Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

### Remarks

Option and Component maps setting to `DBUGetInfo` or `DBUSetInfo` calls.

### See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetCategoryList\(\)](#)

---

PvGetSettingList()  
PvDisconnect()  
PvStop()

---

## PvGetSettingUnits()

Retrieves default units and suggested factor. This function is only valid for settings of long integer type.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSettingUnits(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_ULONG_PTR     pBufSize,  
    BTI_CHAR_PTR      pValue,  
    BTI_ULONG_PTR     pFactor,  
    BTI_ULONG_PTR     pFBufSize,  
    BTI_CHAR_PTR      pFValue);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer allocated to receive string of default units. Receives actual size of string of default units. The size should include the NULL terminator.
Out	<i>pValue</i>	String of default value returned.
Out	<i>pFactor</i>	Address of an unsigned long for factor.
In/Out	<i>pFBufSize</i>	Address of an unsigned long containing size of buffer allocated to receive string of "factor" units. Receives actual size of string of default units. The size should include the NULL terminator.
Out	<i>pFValue</i>	String of "factor" value returned.

---

## Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The setting requested is not of long integer type.
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in <i>pBufSize</i> .
P_E_FAIL	Failed to connect to the named server.

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetCategoryList\(\)](#)  
[PvGetSettingList\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvGetSettingUnitsSize()

Returns the size in bytes of buffer size required to receive information in [PvGetSettingUnits\(\)](#) call.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav78.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSettingUnitsSize(  
    BTI_LONG      hConnection,  
    BTI_ULONG    settingID,  
    BTI_ULONG_PTR pBufSize,  
    BTI_ULONG_PTR pFBufSize);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing size of the buffer allocated to receive string of default units. Receives actual size of string of default units. The size should include the NULL terminator.
In/Out	<i>pFBufSize</i>	Address of an unsigned long containing size of buffer allocated to receive string of "factor" units. Receives actual size of string of default units. The size should include the NULL terminator.

### Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The setting requested is not of long integer type.



---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetSQLConnectionsData()

Retrieves the number of connections to the SQL Connection Manager and all information related to the connections.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetSQLConnectionsData(  
    BTI_LONG      hConnection,  
    BTI_ULONG_PTR pCount);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
Out	<i>pCount</i>	Address of an unsigned long to receive the number of SQL connections.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_FAIL	Failed for other reasons.

### Remarks

The information will be cached by DTI for subsequent calls related to SQL connections. This function should be called first before calling any other functions to get SQL connection information.

The following preconditions must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

The following post conditions must be met:

- The caller should call [PvFreeSQLConnectionsData\(\)](#) to free the cached information when it is no longer needed.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetMkdeCommStat\(\)](#)

[PvGetSQLConnectionInfo\(\)](#)

[PvFreeSQLConnectionsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvGetSQLConnectionInfo()

Query the information for a SQL connection.

Header File: `monitor.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvGetSQLConnectionInfo(  
    BTI_LONG      hConnection,  
    BTI_ULONG     sequence,  
    PVSQCONNINFO* pSQLConnInfo);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>sequence</i>	The sequence number (zero based) of the SQL connection. Must be within a valid range with upper limit defined by the number of SQL connections obtained by <a href="#">PvGetSQLConnectionsData()</a> .
Out	<i>pSQLConnInfo</i>	Address of a <a href="#">PVSQCONNINFO</a> structure to receive the information on the SQL connection.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	<i>hConnection</i> parameter is not a valid connection handle.
P_E_DATA_UNAVAILABLE	Data not available for the SQL connection.
P_E_NULL_PTR	<i>pSQLConnInfo</i> pointer is NULL.
P_E_INVALID_SEQUENCE	Sequence number is not valid.
P_E_FAIL	Failed to disconnect to the named server.

## Remarks

The following preconditions must be met:

- 
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
  - Data for SQL connections retrieved by calling [PvGetSQLConnectionsData\(\)](#)
  - Caller already has a valid SQL connection sequence.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetSQLConnectionsData\(\)](#)

[PvFreeSQLConnectionsData\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetStringType()

Retrieves additional information about PVSETTING\_STRING setting which only applies to string type setting.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetStringType(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID,  
    BTI_ULONG_PTR pTypeString);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pTypeString</i>	Subtype of PVSETTING_STRING returned.

### Return Values

P_OK	The operation was successful.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The setting requested is not of string type.
P_E_FAIL	Failed for other reasons.

### Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

Here are possible subtypes of PVSETTING\_STRING:

- PVSTRING – a string that is neither dir or file
- PVFILESTRING – a string that indicates the path to a file
- PVDIRECTORYSTRING – a string that indicates a directory

The subtypes are defined in config.h.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetStringValue\(\)](#)

[PvSetStringValue\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetStringValue()

Retrieves the value (Null terminated string) for a string type setting, from the data source specified by *whichData*. Some settings may return a list of strings separated by semicolons (;).

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetStringValue(  
    BTI_LONG          hConnection,  
    BTI_ULONG        settingID,  
    BTI_ULONG_PTR    pBufSize,  
    BTI_CHAR_PTR     value,  
    BTI_SINT         whichData);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing the size of the buffer allocated to receive the setting value. Receives the actual size of setting value.
Out	<i>value</i>	Address of a long integer variable that receives the setting value.
In	<i>whichData</i>	Flag to indicate which value is requested: PVDATA_DEFAULT returns default value. PVDATA_CURRENT returns current value

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The requested setting is not of string type.

---



---

P_E_BUFFER_TOO_SMALL	Allocated buffer is too small for the string (the return string is truncated). In this case, the required size is returned in <i>pBufSize</i> .
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetCategoryList\(\)](#)  
[PvGetSettingList\(\)](#)  
[PvGetStringType\(\)](#)  
[PvSetStringValue\(\)](#)  
[PvGetStringValueSize\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvGetStringValueSize()

Retrieves the value (Null terminated string) for a string type setting, from the data source specified by *whichData*. Some settings may return a list of strings separated by semicolons (;).

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetStringValueSize(  
    BTI_LONG          hConnection,  
    BTI_ULONG        settingID,  
    BTI_ULONG_PTR    pBufSize,  
    BTI_SINT         whichData);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In/Out	<i>pBufSize</i>	Address of an unsigned long containing the size of the buffer allocated to receive the setting value. Receives the actual size of setting value.
In	<i>whichData</i>	Flag to indicate which value is requested: PVDATA_DEFAULT returns default value. PVDATA_CURRENT returns current value

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The requested setting is not of string type.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetStringType\(\)](#)

[PvSetStringValue\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvGetTable()

Returns table attributes for a given table.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
RESULT PvGetTable(  
    WORD          dictHandle,  
    LPSTR         tableName,  
    TABLEINFO**  tableProps,  
    COLUMNMAP**  columnList,  
    WORD*         columnCount,  
    INDEXMAP**   indexList,  
    WORD*         indexCount);
```

---

## Arguments

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Name of table to retrieve.
Out	<i>tableProps</i>	Structure containing table information.
Out	<i>columnList</i>	Array of columns defined in the table.
Out	<i>columnCount</i>	Number of columns in <i>columnList</i> .
Out	<i>indexList</i>	Array of segments defined in the table.
Out	<i>indexCount</i>	Number of indexes in the <i>indexList</i> array.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	A general failure occurred
PCM_errMemoryAllocation	Error during memory allocation
PCM_errInvalidDictionaryHandle	The specified dictionary handle does not exist.

## Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

TableProps, indexList, and columnList arrays will need to be released using [PvFreeTable](#).

## See Also

[PvStart\(\)](#)  
[PvOpenDatabase\(\)](#)  
[PvGetTableNames\(\)](#)  
[PvFreeTable\(\)](#)  
[PvFreeTableNames\(\)](#)  
[PvCloseDictionary\(\)](#)  
[PvStop\(\)](#)

---

## PvGetTableNames()

Returns table names of all the tables in the open data dictionary.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT PvGetTableNames(  
    WORD          dictHandle,  
    TABLEMAP**  tableList,  
    WORD*        tableCount);
```

### Arguments

In	<i>dictHandle</i>	Handle of an open dictionary returned by <a href="#">PvOpenDatabase()</a> .
Out	<i>tableList</i>	Array of <a href="#">TABLEMAP</a> structures that contain table names.
Out	<i>tableCount</i>	Number of table names returned in <i>tableList</i> .

### Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errInvalidDictionaryHandle	The specified dictionary handle obtained by <a href="#">PvOpenDatabase()</a> is invalid.

### Remarks

You must first open a dictionary successfully using [PvOpenDatabase\(\)](#).

TableList array will need to be released using [PvFreeTableNames\(\)](#).

You can retrieve more information about a specific table using [PvGetTable\(\)](#).

---

## See Also

[PvStart\(\)](#)

[PvOpenDatabase\(\)](#)

[PvGetTable\(\)](#)

[PvFreeTable\(\)](#)

[PvFreeTableNames\(\)](#)

[PvCloseDictionary\(\)](#)

[PvStop\(\)](#)

---

## PvGetTableStat()

Returns statistical information on a given table.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT DDFAPICALLTYPE PvGetTableStat(  
    BTI_WORD             dbHandle,  
    const BTI_CHAR*     tableName,  
    TABLESTAT*         tableStat);
```

### Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Table name for which you want statistical information.
Out	<i>tableStat</i>	<a href="#">TABLESTAT</a> structure containing table statistics information.

### Return Values

<code>PCM_Success</code>	The operation was successful.
<code>PCM_errFailed</code>	The operation was not successful.
<code>PCM_errMemoryAllocation</code>	An error occurred during memory allocation.
<code>PCM_errInvalidDictionaryHandle</code>	The specified dictionary handle obtained by <a href="#">PvOpenDatabase()</a> is invalid.
<code>PCM_errTableNotFound</code>	The specified table was not found.

### Remarks

You must first obtain a database handle using [PvOpenDatabase\(\)](#).

You can retrieve more information about a specific table using [PvGetTable\(\)](#).



---

If the number of records in the data file is greater than the maximum value that the TABLESTAT structure can return, then the maximum possible value is returned instead, which is 65535 as a 2-byte unsigned integer.

## See Also

[PvCloseDatabase\(\)](#)  
[PvFreeTable\(\)](#)  
[PvFreeTableNames\(\)](#)  
[PvGetTable\(\)](#)  
[PvGetTableStat2\(\)](#)  
[PvGetTableStat3\(\)](#)  
[PvOpenDatabase\(\)](#)  
[PvStart\(\)](#)  
[PvStop\(\)](#)

---

## PvGetTableStat2()

Returns statistical information on a given table, including whether its data file is using compressed data pages. See also [Creating a File with Page Level Compression](#) in *Zen Programmer's Guide* and [Record and Page Compression](#) in *Advanced Operations Guide*.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT DDFAPICALLTYPE PvGetTableStat2 (
    BTI_WORD          dbHandle,
    const BTI_CHAR*   tableName,
    TABLESTAT2*     tableStat2);
```

### Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Table name for which you want statistical information.
Out	<i>tableStat</i>	<a href="#">TABLESTAT2</a> structure containing table statistics information.

### Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errInvalidDictionaryHandle	The specified dictionary handle obtained by <a href="#">PvOpenDatabase()</a> is invalid.
PCM_Success	The operation was successful.

### Remarks

You must first obtain a database handle using [PvOpenDatabase\(\)](#).

You can retrieve more information about a specific table using [PvGetTable\(\)](#).

---

For more information see [Differences Between TABLESTAT2 and TABLESTAT](#).

If the number of records in the data file is greater than the maximum value that the TABLESTAT2 structure can return, then the maximum possible value is returned instead, which is 2,147,483,647 as a 4-byte signed integer.

## See Also

[PvGetTable\(\)](#)

[PvGetTableStat\(\)](#)

[PvGetTableStat3\(\)](#)

[PvStart\(\)](#)

[PvOpenDatabase\(\)](#)

[PvOpenDatabase\(\)](#)

[PvGetTable\(\)](#)

[PvFreeTable\(\)](#)

[PvFreeTableNames\(\)](#)

[PvCloseDictionary\(\)](#)

[PvCloseDatabase\(\)](#)

[PvStop\(\)](#)

---

## PvGetTableStat3()

Returns statistical information on a given table, including a 64-bit record count capable of indicating up to  $2^{63}-1$  records, or 9223372036854775807.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
PRESULT DDFAPICALLTYPE PvGetTableStat3 (
    BTI_WORD          dbHandle,
    const BTI_CHAR*   tableName,
    TABLESTAT3*     tableStat3);
```

### Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>tableName</i>	Table name for which you want statistical information.
Out	<i>tableStat</i>	<a href="#">TABLESTAT3</a> structure containing table statistics information.

### Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errInvalidDictionaryHandle	The specified dictionary handle obtained by <a href="#">PvOpenDatabase()</a> is invalid.
PCM_errTableNotFound	The specified table was not found

### Remarks

You must first obtain a database handle using [PvOpenDatabase\(\)](#).

You can retrieve more information about a specific table using [PvGetTable\(\)](#).

---

For more information see [Differences Between TABLESTAT3 and TABLESTAT2](#).

## See Also

[PvGetTable\(\)](#)  
[PvGetTableStat\(\)](#)  
[PvGetTableStat2\(\)](#)  
[PvStart\(\)](#)  
[PvOpenDatabase\(\)](#)  
[PvOpenDatabase\(\)](#)  
[PvGetTable\(\)](#)  
[PvFreeTable\(\)](#)  
[PvFreeTableNames\(\)](#)  
[PvCloseDictionary\(\)](#)  
[PvCloseDatabase\(\)](#)  
[PvStop\(\)](#)

---

## PvGetValueLimit()

Retrieves upper and lower limits for settings of long type.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvGetValueLimit(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_LONG_PTR      pMaxValue,  
    BTI_LONG_PTR      pMinValue);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
Out	<i>pMaxValue</i>	Address of a long integer that receives the upper limit value. If NULL is passed here, no value will be returned.  If a negative value is returned, interpret it as follows: /* Maximum valid memory or disk size */P_MAX_MEM_DISK_SIZE - 129 /* Maximum size limited by available disk space */ P_MAX_LIMITED_BY_DISK -2 /* Maximum size limited by available memory */ P_MAX_LIMITED_BY_MEMORY -1
Out	<i>pMinValue</i>	Address of a long integer that receives the lower limit value. If NULL is passed here, no value will be returned.

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.

---

---

P_E_INVALID_DATA_TYPE	The requested setting is not of long type.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetLongValue\(\)](#)

[PvSetLongValue\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvIsDatabaseSecured()

Determines whether a given database has security enabled.

Header File: dtisecurity.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvIsDatabaseSecured(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbName,  
    BTI_LONG_PTR     dbAuthentication);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database to check.
Out	<i>dbAuthentication</i>	2 if database is secured using domain authentication 1 if database is secured using Zen database authentication 0 if database is not secured

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_FAIL	Failed to open the database for other reasons.

### Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).



- 
- Connection established by [PvConnectServer\(\)](#), or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvOpenDatabase\(\)](#)

[PvSecureDatabase\(\)](#)

[PvSecureDatabase2\(\)](#)

[PvUnSecureDatabase\(\)](#)

[PvCloseDatabase\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvIsSettingAvailable()

Query to see if a setting is available for configuring.

Header File: `config.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvIsSettingAvailable(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting.

### Return Values

Zero	Setting is unavailable.
Non-zero	Setting is available.

### Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

Setting may be unavailable due to insufficient rights to access the setting or if no such setting ID exist.

### See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

---

PvGetCategoryList()  
PvGetSettingList()  
PvDisconnect()  
PvStop()

---

## PvListDSNs()

Retrieves the list of system datasource names (DSN) of type Pervasive ODBC Engine Interface.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

### Syntax

```
BTI_API PvListDSNs(  
    BTI_LONG          hConnection,  
    BTI_ULONG_PTR    pdsnListSize,  
    BTI_CHAR_PTR     pdsnList,  
    BTI_CHAR         filtering);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In/Out	<i>pdsnListSize</i>	Address of an unsigned long containing the size of the buffer for the list of DSNs. Receives actual size of the returned DSN list.
Out	<i>pdsnList</i>	Contains the list of DSNs if successful.
In	<i>filtering</i>	Set to 1 if you want only Zen DSNs. Set to 0 if you want all DSNs.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_BUFFER_TOO_SMALL	The buffer is too small for the string. In this case, the required buffer size is returned in <i>pdsnListSize</i> .
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

To retrieve the list of DSNs without having to prompt the user to login, pass empty strings for username and password when establishing the server connection with [PvConnectServer\(\)](#).

**Note:** The connection established by passing empty strings for username and password is an insecure connection, and will not have sufficient rights to perform most of the other operations in DTI.

## Example

```
BTI_WORD           res = 0;
BTI_ULONG          dsncount = 0;
BTI_ULONG          dsnListSize = 0;
BTI_CHAR           * dsnList;

// MAX_DSN_NAME_LENGTH is defined to be 32
// in catalog.h
res = PvCountDSNs (hConnection,
                  &dsnCount,
                  1);
dsnListSize = dsnCount * (MAX_DSN_NAME_LENGTH+1);
dsnList = new char[dsnListSize];
res = PvListDSNs (hConnection,
                 &dsnListSize,
                 dsnList,
                 1);
```

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvCountDSNs\(\)](#)  
[PvGetDSN\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)

---

## PvModifyDatabase()

Modify an existing database using the specified information for the new database name, dictionary and data paths and the database flag.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvModifyDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbNameExisting,  
    BTI_CHAR_PTR     dbNameNew,  
    BTI_CHAR_PTR     dictPath,  
    BTI_CHAR_PTR     dataPath,  
    BTI_ULONG        dbFlags);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbNameExisting</i>	Name of the existing database
In	<i>dbNameNew</i>	Name of the new database. Set this parameter to NULL if you want the database name to remain unchanged.
In	<i>dictPath</i>	Dictionary path.
In	<i>dataPath</i>	Data path. Set this value to NULL to use the default data path (that is, the same as the dictionary path) If you want to modify a database to include MicroKernel Engine data files located in multiple paths, specify this parameter as a semicolon (;) delimited list. For example: C:\data\path1;C:\data\path2

---

In	<i>dbFlags</i>	<p>Database flags, which can be a combination of the P_DBFLAG_ constants.</p> <ul style="list-style-type: none"> <li>• P_DBFLAG_RI (enforce integrity constraints, including referential integrity and triggers)</li> <li>• P_DBFLAG_BOUND (stamps the database name on the dictionary files so only that database can use them)</li> <li>• P_DBFLAG_DBSEC_AUTHENTICATION (use database security authentication, Mixed security policy. See <a href="#">Btrieve Security Policy</a>.)</li> <li>• P_DBFLAG_DBSEC_AUTHORIZATION (use database security authorization, Database security policy. See <a href="#">Btrieve Security Policy</a>.)</li> <li>• P_DBFLAG_LONGMETADATA (use V2 metadata. See <a href="#">Metadata Version</a>.)</li> </ul>
----	----------------	--

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_ACCESS_RIGHT	Insufficient access right for the operation
P_E_NOT_EXIST	Named database does not exist on the server.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#), or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

## Retrieve Security Policy

The following table indicates how to specify a security model in a new database, or to interpret the security model of an existing database. Using any other combination of flags for security will result in status code 7024.

This Flag Combination	Represents This Security Model
No flags	Classic
P_DBFLAG_DBSEC_AUTHENTICATION	Mixed
P_DBFLAG_DBSEC_AUTHENTICATION P_DBFLAG_DBSEC_AUTHORIZATION	Database

## See Also

- [PvStart\(\)](#)
- [PvConnectServer\(\)](#)
- [PvCreateDatabase\(\)](#)
- [PvGetDbNamesData\(\)](#)
- [PvGetDbName\(\)](#)
- [PvGetDbFlags\(\)](#)
- [PvGetDbDataPath\(\)](#)
- [PvGetDbDictionaryPath\(\)](#)
- [PvGetDbServerName\(\)](#)
- [PvFreeDbNamesData\(\)](#)
- [PvDisconnect\(\)](#)
- [PvStop\(\)](#)



---

## PvModifyDatabase2()

Modify an existing database using the specified information for the new database name, dictionary and data paths, database flag, and code page. This function is the same as [PvModifyDatabase\(\)](#) except that the database code page is also specified.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvModifyDatabase2(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR     dbNameExisting,  
    BTI_CHAR_PTR     dbNameNew,  
    BTI_CHAR_PTR     dictPath,  
    BTI_CHAR_PTR     dataPath,  
    BTI_ULONG        dbFlags,  
    BTI_LONG         dbCodePage);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbNameExisting</i>	Name of the existing database
In	<i>dbNameNew</i>	Name of the new database. Set this parameter to NULL if you want the database name to remain unchanged.
In	<i>dictPath</i>	Dictionary path.
In	<i>dataPath</i>	Data path. Set to NULL to use the default data path (that is, the same as the dictionary path) If you want to modify a database to include MicroKernel Engine data files located in multiple paths, specify this parameter as a semicolon (;) delimited list. For example: <code>C:\data\path1;C:\data\path2</code>

---

---

In	<i>dbFlags</i>	<p>Database flags, which can be a combination of the P_DBFLAG_ constants.</p> <ul style="list-style-type: none"> <li>• P_DBFLAG_RI (enforce integrity constraints, including referential integrity and triggers)</li> <li>• P_DBFLAG_BOUND (stamps the database name on the dictionary files so only that database can use them)</li> <li>• P_DBFLAG_DBSEC_AUTHENTICATION (use database security authentication, Mixed security policy. See <a href="#">Retrieve Security Policy</a>.)</li> <li>• P_DBFLAG_DBSEC_AUTHORIZATION (use database security authorization, Database security policy. See <a href="#">Retrieve Security Policy</a>.)</li> <li>• P_DBFLAG_LONGMETADATA (use V2 metadata. See <a href="#">Metadata Version</a>.)</li> </ul>
In	<i>dbCodePage</i>	<p>For databases on Windows platforms, a number indicating the code page for database data and metadata strings.</p> <p>For databases on Linux and macOS distributions, one of the following to indicate the code page for database data and metadata strings:</p> <ul style="list-style-type: none"> <li>• P_DBCODEPAGE_UTF8</li> <li>• P_DBCODEPAGE_EUCJP</li> <li>• P_DBCODEPAGE_ISO8859_1</li> </ul> <p>For databases on Windows, Linux, and macOS, the value can also be a zero or P_DBCODEPAGE_NA.</p> <p>A zero indicates legacy behavior. That is, no code page is specified, defaulting to the operating system encoding on the server machine. See also the <a href="#">Code Page</a> database property in <i>Zen User's Guide</i>.</p> <p>P_DBCODEPAGE_NA specifies to leave the code page as is (the database code page is not to be changed).</p> <p><b>Note:</b> The database engine does <b>not</b> validate the encoding of the data and metadata that an application inserts into a database. The engine assumes that all data was entered using the encoding of the server or the client as explained under <a href="#">Database Code Page and Client Encoding</a> in <i>Advanced Operations Guide</i>.</p>

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer
P_E_ACCESS_RIGHT	Insufficient access right for the operation

---

---

P_E_NOT_EXIST	Named database does not exist on the server.
P_E_FAIL	Failed for other reasons.

---

## Remarks

The following precondition must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#), or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## Btrieve Security Policy

See [Btrieve Security Policy](#).

## See Also

[PvConnectServer\(\)](#)  
[PvCreateDatabase2\(\)](#)  
[PvCreateDSN2\(\)](#)  
[PvDisconnect\(\)](#)  
[PvFreeDbNamesData\(\)](#)  
[PvGetDbCodePage\(\)](#)  
[PvGetDbDataPath\(\)](#)  
[PvGetDbDictionaryPath\(\)](#)  
[PvGetDbFlags\(\)](#)  
[PvGetDbName\(\)](#)  
[PvGetDbNamesData\(\)](#)  
[PvGetDbServerName\(\)](#)  
[PvGetDSNEx2\(\)](#)  
[PvModifyDSN2\(\)](#)  
[PvStart\(\)](#)  
[PvStop\(\)](#)

---

# PvModifyDSN()

Modifies an existing data source name.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav78.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

## Syntax

```
BTI_API PvModifyDSN(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  pdsnName,  
    BTI_CHAR_PTR  pdsnDesc,  
    BTI_CHAR_PTR  pdsnDBQ,  
    BTI_LONG      openMode);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pdsnName</i>	Name of the DSN to modify.
In	<i>pdsnDesc</i>	New description for the DSN.
In	<i>pdsnDBQ</i>	New Database name for the DSN.
In	<i>openMode</i>	New Open mode for the DSN, which is one of the following: NORMAL_MODE ACCELERATED_MODE, READONLY_MODE EXCLUSIVE_MODE See also <a href="#">DSN Open Mode</a> in <i>ODBC Guide</i> .

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.

---

---

P_E_NULL_PTR	Call with NULL pointer.
P_E_DSN_DOES_NOT_EXIST	The specified DSN name does not exist.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_INVALID_OPEN_MODE	The specified open mode is invalid.
P_E_FAIL	Failed to retrieve data path.

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvListDSNs\(\)](#)  
[PvCreateDSN\(\)](#)  
[PvGetDSN\(\)](#)  
[PvGetDSNEx\(\)](#)  
[PvDeleteDSN\(\)](#)  
[PvCountDSNs\(\)](#)  
[PvStop\(\)](#)

---

## PvModifyDSN2()

Modifies an existing data source name. This function is the same as [PvModifyDSN\(\)](#) except that the encoding option for data is also specified.

Header File: `catalog.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

This function is deprecated in Zen v11 and higher versions. Use the ODBC API to work with client DSNs.

### Syntax

```
BTI_API PvModifyDSN(  
    BTI_LONG      hConnection,  
    BTI_CHAR_PTR  pdsnName,  
    BTI_CHAR_PTR  pdsnDesc,  
    BTI_CHAR_PTR  pdsnDBQ,  
    BTI_LONG      openMode,  
    BTI_LONG      translate);
```

---

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>pdsnName</i>	Name of the DSN to modify.
In	<i>pdsnDesc</i>	New description for the DSN.
In	<i>pdsnDBQ</i>	New Database name for the DSN.
In	<i>openMode</i>	Open mode for the DSN, which is one of the following: <ul style="list-style-type: none"><li>• NORMAL_MODE</li><li>• ACCELERATED_MODE</li><li>• READONLY_MODE</li><li>• EXCLUSIVE_MODE</li></ul> See also <a href="#">DSN Open Mode</a> in <i>ODBC Guide</i> .
In	translate	Encoding option for data, which can be one of the following: <ul style="list-style-type: none"><li>• DSNFLAG_DEFAULT</li><li>• DSNFLAG_OEMANSI</li><li>• DSNFLAG_AUTO</li></ul> See also <a href="#">Encoding Translation</a> in <i>ODBC Guide</i> . Note that DSNFLAG_DEFAULT corresponds to the "None" encoding option in ODBC Administrator.

---

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_DSN_DOES_NOT_EXIST	The specified DSN name does not exist.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_INVALID_OPEN_MODE	The specified open mode is invalid.
P_E_INVALID_TRANSLATE_OPTION	The specified encoding translation option is invalid.
P_E_FAIL	Failed to retrieve data path.

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.

## See Also

[PvConnectServer\(\)](#)

[PvCountDSNs\(\)](#)

[PvCreateDatabase2\(\)](#)

[PvCreateDSN2\(\)](#)

[PvDeleteDSN\(\)](#)

[PvGetDSN\(\)](#)

[PvGetDSNEx2\(\)](#)

[PvListDSNs\(\)](#)

[PvStart\(\)](#)

[PvStop\(\)](#)



---

# PvOpenDatabase()

Opens a database by name and returns a handle that can be used to manipulate the database catalog.

Header File: catalog.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvOpenDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_CHAR_PTR      dbUser,  
    BTI_CHAR_PTR      dbPassword,  
    BTI_WORD_PTR      dbHandle);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>dbName</i>	Name of the database.
In	<i>dbUser</i>	Database user name if security is defined.
In	<i>dbPassword</i>	Database password if security is defined.
Out	<i>dbHandle</i>	Returned handle to the database.

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_FAIL	Failed to open the database for other reasons.
PCM_errSessionSecurityError	Invalid user name or password.

---

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#)
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- If the database has security enabled, you must specify a valid database user name and password. Security for the returned database handle is enforced based on the access rights defined for the database, and should match behavior seen in SQL or ODBC access methods.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetDbFlags\(\)](#)

[PvModifyDatabase\(\)](#)

[PvCloseDatabase\(\)](#)

[PvDropDatabase\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvOpenDictionary()

Opens an existing dictionary. Given an absolute path of the dictionary or data source names, it returns a dictionary handle that will be used for any subsequent calls to any functions.

**Note:** This function is deprecated in Zen 9 and higher versions. See [PvOpenDatabase\(\)](#) to replace this function in your application.

Header File: ddf.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
PRERESULT PvOpenDictionary(  
    LPTSTR      path,  
    WORD*       dictHandle,  
    LPSTR       user,  
    LPSTR       password);
```

### Arguments

In	<i>path</i>	Fully-qualified path to the dictionary files.
Out	<i>dictHandle</i>	Handle to be used in subsequent calls
In	<i>user</i>	User name needed to open the dictionary. This argument can be set to NULL.
In	<i>password</i>	Used in conjunction with user name to open the dictionary files. Can also be NULL.

### Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errMemoryAllocation	An error occurred during memory allocation.
PCM_errDictionaryPathNotFound	The specified dictionary path is invalid.
PCM_errDictionaryAlreadyOpen	The specified dictionary files are currently open.
PCM_SessionSecurityError	Either the user name or password is invalid.

---

## Remarks

This function should be called first when accessing DDFs via DTI.

Multiple dictionaries can be open at one time.

Use `PvCloseDictionary()` to free the resources.

## See Also

`PvStart()`

`PvCreateDictionary()`

`PvCreateDatabase()`

`PvCloseDictionary()`

`PvStop()`

---

# PvRemoveUserFromGroup()

Remove an existing user from an existing group.

Header File: `ddf.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav90.dll` (Windows), `libpsqltdi.so` (Linux), `libpsqltdi.dylib` (macOS) (See also [Link Libraries](#))

## Syntax

```
PRESULT DDFAPICALTYPE PvRemoveUserFromGroup(  
    BTI_WORD            dbHandle,  
    const BTI_CHAR*    user);  
    const BTI_CHAR*    group,
```

## Arguments

In	<i>dbHandle</i>	Handle of an open database returned by <a href="#">PvOpenDatabase()</a> .
In	<i>user</i>	Database user name.
In	<i>group</i>	Database group name.

## Return Values

PCM_Success	The operation was successful.
PCM_errFailed	The operation was not successful.
PCM_errInvalidAccountName	The specified account or user name does not exist.
PCM_errUserNotPartOfGroup	The specified user is not a member of the group.
PCM_errDatabaseHasNoSecurity	Database has no security.
PCM_errSessionSecurityError	Database opened with insufficient privilege.

## Remarks

The following preconditions must be met:

- You must first open a database successfully using [PvOpenDatabase\(\)](#) as user 'Master'.
- The associated database has database-level security enabled.

- 
- The specified group and user names must already exist in the database.
  - The specified user is a member of the specified group.

The following post condition must be met:

- Use [PvCloseDatabase\(\)](#) to free the resources.

## See Also

[PvCreateGroup\(\)](#)

[PvCreateUser\(\)](#)

[PvAlterUserName\(\)](#)

[PvAddUserToGroup\(\)](#)

[PvDropGroup\(\)](#)

[PvDropUser\(\)](#)

[PvOpenDatabase\(\)](#)

[PvCloseDatabase\(\)](#)

---

# PvSecureDatabase()

Enables security for an existing database.

Header File: dtisecurity.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvSecureDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_CHAR_PTR      dbUser,  
    BTI_CHAR_PTR      dbPassword);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <b>PvConnectServer()</b> function.
In	<i>dbName</i>	Name of the database.
In	<i>dbUser</i>	Database user name – must be Master to set security.
In	<i>dbPassword</i>	Database password for Master user.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_FAIL	Failed to open the database for other reasons.
PCM_errSessionSecurityError	Invalid user name or password.

## Remarks

The following preconditions must be met:

- 
- DTI session started by calling [PvStart\(\)](#).
  - Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
  - When you enable security, you must specify Master as the database user name and choose a password. Security for the database is enforced based on the access rights defined for the database and should match behavior seen in SQL or ODBC access methods.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvOpenDatabase\(\)](#)

[PvUnSecureDatabase\(\)](#)

[PvIsDatabaseSecured\(\)](#)

[PvCloseDatabase\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)



---

## PvSecureDatabase2()

Enables database security for an existing database. It differs from PvSecureDatabase() in that it supports domain authentication.

Header File: dtisecurity.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvSecureDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_CHAR_PTR      dbPassword,  
    BTI_LONG          dbAuthentication);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <b>PvConnectServer()</b> function.
In	<i>dbName</i>	Name of the database.
In	<i>dbPassword</i>	Database password for Master user.
In	<i>dbAuthentication</i>	Type of authentication to enable. Values are 1 for database and 2 for domain.

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_FAIL	Failed to open the database for other reasons.
PCM_errSessionSecurityError	Invalid password.

---

## Remarks

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- When you enable security, you must choose a password for the Master user. Security for the database is enforced based on the access rights defined for the database and should match behavior seen in SQL or ODBC access methods.
- You must be connecting to a Windows server. Calls to Linux or macOS servers return a general failure (status code 7004), since Active Directory domain authentication is Windows only.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvOpenDatabase\(\)](#)

[PvSecureDatabase\(\)](#)

[PvUnSecureDatabase\(\)](#)

[PvIsDatabaseSecured\(\)](#)

[PvCloseDatabase\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvSetBooleanValue()

Save new value for a Boolean type setting, to the data target specified by *whichData*.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvSetBooleanValue(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_SINT          newValue,  
    BTI_SINT          whichData);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In	<i>newValue</i>	Integer value to be set.
In	<i>whichData</i>	Flag to indicate which value is to be set: <ul style="list-style-type: none"><li>• PVDATA_CURRENT means apply setting changes to current session and save to registry, ini or ncf file. Only valid for Trace Op in Btr 6.15 NT release.</li><li>• PVDATA_PERSISTENT don't apply setting change to the current session. Save setting to registry, ini or ncf files only.</li></ul>

---

### Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_INVALID_DATA_TYPE	The setting is not of Boolean type.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- You must logon with administrator-level rights with PvConnectServer () before you can set a new value for a Boolean type setting.

**Note:** This function cannot be called by a user logged-in with the "restricted" user type.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetBooleanValue\(\)](#)

[PvGetBooleanStrings\(\)](#)

[PvIsSettingAvailable\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvSetLongValue()

Save new value for a long integer type setting, to the data target specified by *whichData*.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvSetLongValue(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID,  
    BTI_LONG      newValue,  
    BTI_SINT      whichData);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In	<i>newValue</i>	Integer value to be set. Before calling this function, check to see that the value is within the limits for the particular setting by using the <a href="#">PvGetValueLimit()</a> function.
In	<i>whichData</i>	Flag to indicate which value is to be set: PVDATA_CURRENT sets current value. PVDATA_PERSISTENT sets persistent value

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_INVALID_DATA_TYPE	The setting is not of long type.
P_E_OUT_OF_RANGE	The value specified to be set is out of range.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
- You must logon with administrator-level rights with `PvConnectServer ()` before you can set a new value for a Long type setting.

**Note:** This function cannot be called by a user logged-in with the "restricted" user type.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetLongValue\(\)](#)

[PvGetValueLimit\(\)](#)

[PvIsSettingAvailable\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvSetSelectionValue()

Save new value for a selection type setting, to the data target specified by *whichData*.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvSetSelectionValue(  
    BTI_LONG          hConnection,  
    BTI_ULONG         settingID,  
    BTI_ULONG         numItems,  
    BTI_LONG_PTR      pNewValue,  
    BTI_SINT          whichData);
```

### Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In	<i>numItems</i>	Number of individual selection items to be set.
In	<i>pNewValue</i>	Array of individual selection items to be set.
In	<i>whichData</i>	Flag to indicate which value is to be set: PVDATA_CURRENT sets current value. PVDATA_PERSISTENT sets persistent value

### Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The setting is not of selection type.
P_E_INVALID_SELECTION	At least one selection item is invalid.
P_E_FAIL	Failed for other reasons.

---

## Remarks

This function is used to work with both single-selection and multi-selection data types. If more than one selection items are set for a single-selection item, the first value is used.

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- You must logon with administrator-level rights with PvConnectServer () before you can set a new value for a Selection type setting.

**Note:** This function cannot be called by a user logged-in with the "restricted" user type.

## See Also

[PvStart\(\)](#)  
[PvConnectServer\(\)](#)  
[PvGetCategoryList\(\)](#)  
[PvGetSettingList\(\)](#)  
[PvGetSelectionValue\(\)](#)  
[PvGetSelectionString\(\)](#)  
[PvGetAllPossibleSelections\(\)](#)  
[PvCountSelectionItems\(\)](#)  
[PvIsSettingAvailable\(\)](#)  
[PvDisconnect\(\)](#)  
[PvStop\(\)](#)



---

# PvSetStringValue()

Save new value for a string type setting, to the data target specified by *whichData*.

Header File: config.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqltdi.so (Linux), libpsqltdi.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvSetStringValue(  
    BTI_LONG      hConnection,  
    BTI_ULONG     settingID,  
    BTI_CHAR_PTR  newValue,  
    BTI_SINT      whichData);
```

## Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
In	<i>settingID</i>	Unique identifier for the setting. A list of settings can be obtained from <a href="#">PvGetSettingList()</a> .
In	<i>newValue</i>	String value to be set.
In	<i>whichData</i>	Flag to indicate which value is to be set: PVDATA_CURRENT sets current value. PVDATA_PERSISTENT sets persistent value

---

## Return Values

---

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_INVALID_DATA_TYPE	The setting is not of string type.
P_E_FAIL	Failed for other reasons.

---

---

## Remarks

Some settings may take multiple strings separated by semicolons (;).

The following preconditions must be met:

- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.
- You must logon with administrator-level rights with [PvConnectServer\(\)](#) before you can set a new value for a String type setting.

**Note:** This function cannot be called by a user logged-in with the "restricted" user type.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvGetCategoryList\(\)](#)

[PvGetSettingList\(\)](#)

[PvGetStringType\(\)](#)

[PvGetStringValue\(\)](#)

[PvIsSettingAvailable\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

# PvStart()

Start a Distributed Tuning Interface (DTI) session. This function must be called before any DTI calls are made.

Header File: connect.h (See also [Header Files](#))

Function First Available In Library: w3dbav75.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_SINT PvStart(BTI_LONG reserved);
```

## Arguments

---

In	<i>reserved</i>	Reserved for future use.
----	-----------------	--------------------------

---

## Return Values

---

P_OK	The operation was successful.
P_E_FAIL	A general failure occurred.

---

## Remarks

This function performs initialization and binds resources for DTI.

## Example

```
BTI_SINT status = 0;
status = PvStart(0);
// invoke multiple DTI calls
status = PvStop (0);
```

## See Also

[PvStop\(\)](#)

---

## PvStop()

Closes a DTI session and frees the related resources.

Header File: `connect.h` (See also [Header Files](#))

Function First Available In Library: `w3dbav75.dll` (Windows), `libpsqldti.so` (Linux), `libpsqldti.dylib` (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_SINT PvStop(BTI_LONG_PTR preserved);
```

### Arguments

---

In	<i>preserved</i>	Reserved for future use.
----	------------------	--------------------------

---

### Return Values

---

P_OK	The operation was successful.
P_E_FAIL	A general failure occurred.

---

### Remarks

This function frees resources of DTI and closes the DTI session. This function should be called before your application exits.

### Example

```
BTI_LONG status = 0;  
status = PvStop(0);
```

### See Also

[PvStart\(\)](#)

---

# PvUnSecureDatabase()

Disables database security on a database.

Header File: dtisecurity.h (See also [Header Files](#))

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

## Syntax

```
BTI_API PvUnSecureDatabase(  
    BTI_LONG          hConnection,  
    BTI_CHAR_PTR      dbName,  
    BTI_CHAR_PTR      dbUser,  
    BTI_CHAR_PTR      dbPassword);
```

## Arguments

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <b>PvConnectServer()</b> function.
In	<i>dbName</i>	Name of the database.
In	<i>dbUser</i>	Database user name - must be Master to enable or disable security.
In	<i>dbPassword</i>	Database password for Master user.

## Return Values

P_OK	The operation was successful.
P_E_INVALID_HANDLE	Invalid connection handle.
P_E_NULL_PTR	Call with NULL pointer.
P_E_ACCESS_RIGHT	Insufficient access right for the operation.
P_E_FAIL	Failed to open the database for other reasons.
PCM_errSessionSecurityError	Invalid user name or password.

## Remarks

The following preconditions must be met:

- 
- DTI session started by calling [PvStart\(\)](#).
  - Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, `P_LOCAL_DB_CONNECTION` may be used as the connection handle.
  - Database is secured.

## See Also

[PvStart\(\)](#)

[PvConnectServer\(\)](#)

[PvOpenDatabase\(\)](#)

[PvSecureDatabase\(\)](#)

[PvIsDatabaseSecured\(\)](#)

[PvCloseDatabase\(\)](#)

[PvDisconnect\(\)](#)

[PvStop\(\)](#)

---

## PvValidateLicenses()

Initiates a check of the validity of all keys on the computer indicated by the connection.

Header File: dtlicense.h (See also Header Files)

Function First Available In Library: w3dbav90.dll (Windows), libpsqldti.so (Linux), libpsqldti.dylib (macOS) (See also [Link Libraries](#))

### Syntax

```
BTI_API PvValidateLicenses(BTI_LONG hConnection);
```

### Arguments

---

In	<i>hConnection</i>	Connection handle that identifies the server. Connection handles are obtained with the <a href="#">PvConnectServer()</a> function.
----	--------------------	--

---

### Return Values

---

P_OK	The validation operation completed successfully.
P_E_FAIL	The validation operation did not complete successfully.
Status code pertaining to license administration or to authorization	See <i>Status Codes and Messages</i> for <a href="#">License Administrator Status Codes</a> and <a href="#">Authorization Status Codes</a> .

---

### Remarks

PvValidateLicenses returns only the result from *requesting* a validation check. It does *not* return any information about the state of the keys. You must separately call [PvGetProductsInfo\(\)](#) to get the XML string of product information that includes information about the state of the keys.

The following preconditions must be met:

- DTI session started by calling [PvStart\(\)](#).
- Connection established by [PvConnectServer\(\)](#) or if you are performing the operation on a local machine, P\_LOCAL\_DB\_CONNECTION may be used as the connection handle.

---

## Example

```
status = PvValidateLicenses(P_LOCAL_DB_CONNECTION);
```

## See Also

[PvGetProductsInfo\(\)](#)

[PvStart\(\)](#)

[PvStop\(\)](#)



